

Manual COPYRIGHT (C) 2006 NetSupport Ltd. All rights reserved.

The Information in this document is subject to change without notice. NetSupport Ltd. reserves the right to revise this document and to make changes from time to time in the content hereof without obligation to notify any person or persons of such revisions or changes.

The software described in this document is supplied under a licence agreement and is protected by international copyright laws. You may copy it only for the purpose of backup and use it only as described in the Licence agreement.

Any implied warranties including any warranties of merchantability or fitness for a particular purpose are limited to the terms of the express warranties set out in the licence agreement.

Program COPYRIGHT (C) 1991-2006 NetSupport Ltd. All rights reserved.

Trademarks

NetSupport is a registered trademark of NetSupport Ltd.

Windows, Windows 95/98/2000/2003, Millennium (ME), XP, Windows NT and Windows CE are trademarks of Microsoft Corporation.

IBM is a registered trademark of International Business Machines Corporation.

NetWare is a registered trademark of Novell Inc.

Other products, trademarks or registered trademarks are the property of their respective owners.

Software Licence Agreement

Please read this agreement before installing or using your copy of NetSupport Software. This is a legal agreement between you and NetSupport Ltd. If you do not wish to be bound by the terms of this licence agreement you must not load, activate or use the software.

TERM: Subject to termination under Termination Clause below the Licence shall be perpetual.

GRANT OF LICENCE: This software is designed to run on standalone computers and computer networks. You may load the software from a Network File server but you must purchase a licence for each workstation on which you will install or run the software.

COPYRIGHT: This software is protected by international copyright laws. You may copy it only for backup purposes. The software is licensed to you, but not sold to you.

RESTRICTIONS: Neither you nor any reseller may rent, lease, sell licensed copies on approval, or otherwise transfer the right to use this software to another person, except that you may sell or give away your original copy, as long as you do not keep any copies. The software may not be modified, disassembled or reverse engineered except with the prior written consent of NetSupport Ltd.

LIMITED WARRANTY: NetSupport Ltd warrants that the Software will perform substantially in accordance with the accompanying documentation for a period of ninety (90) days from the date of purchase. NetSupport Ltd's entire liability and your exclusive remedy shall be either a) the replacement of the defective software or b) return of the price paid. This remedy shall be at NetSupport Ltd's option and subject to proof of purchase from an authorised source.

Any implied warranties including any warranties of satisfactory quality or fitness for a particular purpose are limited to the terms of the express warranties. NetSupport Ltd shall not in any event be liable for loss of profits, data or information of any kind or for special, incidental, consequential, indirect or other similar damages arising from any breach of these warranties or use of the Software even if they have been advised of the possibility of such damages. Some countries do not allow the limitation or exclusion of incidental or consequential damages, so the above limitation or exclusion may not apply to you. This warranty does not affect your statutory rights and you may have other rights that vary from country to country. In any event NetSupport Ltd's maximum liability shall not exceed the price paid by the end-user / licensee.

TERMINATION: You may terminate this Licence and this Agreement at any time by destroying the Program and its documentation, together with any copies in any form.

NetSupport Ltd may terminate this Licence forthwith by notice in writing to you if you commit any serious breach of any term of this Licence and (in the case of a breach capable of being remedied) shall have failed within 30 days after receipt of a request in writing from NetSupport Ltd so to do, to remedy the breach (such request to contain a warning of NetSupport Ltd's intention to terminate). Upon termination you will destroy or return to NetSupport Ltd the original and all copies of the software and will confirm in writing to NetSupport Ltd that this has been done.

SUPPORT: If you have a problem with the installation of the software you should in the first instance contact your supplier. You can separately purchase support and maintenance which will also cover the supply of enhancements and upgrades.

GOVERNING LAW : This agreement shall be governed by the laws of England.

Contents

Welcome to NetSupport.....	9
About this Manual	9
Conventions Used	10
Terminology Used	10
About NetSupport	11
What is NetSupport Manager?	12
Features	13
Applications.....	17
Installation	18
Planning an Installation	19
Starting the Installation.....	20
Uninstalling NetSupport.....	28
Evaluation Kit	28
Advanced Installation	29
Creating an administrative (network) installation	30
Silent/Unattended Installations.....	31
Install Configuration Options Dialog	32
NetSupport Deploy - NetSupports Remote Install Utility	35
Starting NetSupport Deploy	37
Preparing a Deployment Routine	38
Deploy a NetSupport Package	39
Deploy a Client Configuration.....	43
Deploy a NetSupport License file	44
Remote Uninstall.....	45
Pre-Define Settings For A Future Deployment.....	47
Log Files	48
Installing a NetSupport Client on Pocket PC Devices	50
Installing a NetSupport Client on Linux Platforms	52
Starting the NetSupport Control	54
The Control Window.....	55
Customising the Toolbar.....	58
NetSupport Manager Control Toolbar Buttons	60
The Control Window – Tree View	64
The Control Window – List View	67
Finding Clients	68
Connecting to Clients	70
Quick Connect	71
Connecting to Clients on different Protocols	73

Configuring The NetSupport Control For Subnet Browsing	74
Connecting to Clients/Controls via a NetSupport Gateway	77
Connecting through Firewalls and Proxy Servers	89
Connecting to a MAC Based System	91
Implementing NetSupport in a Terminal Server Environment	92
Disconnecting a Client	94
Disconnecting all Clients	94
Client Automatic Login	95
Client Automatic Update	96
Power Management – Power on/Power off	97
Client Power On	97
Client Power Off	99
Special Considerations on Windows NT 4.0.	99
Rebooting or Logging out Clients	100
Sending Ctrl+Alt+Delete	101
Viewing.....	102
The View Window.....	102
Viewing Clients	104
Viewing Modes.....	104
Maximising the View Area.....	105
Viewing multiple Client screens simultaneously.....	106
Blanking the Clients screen while Viewing.....	106
Scale to Fit Mode	106
Displaying the View Settings for a Client.....	107
Scanning.....	108
Scan one Client screen at a time	108
Scanning Multiple Client Screens	109
The Scan Window.....	110
Thumbnail View / Monitor Mode.....	113
Organising Clients in the List View	115
Launching Applications	116
User Defined Tools	119
Showing the Control screen to Clients	121
Showing a Client's screen on a number of Client screens.....	125
Show Application	126
Audio Support.....	127
Audio Announcements	128
Adjusting Microphone and Speaker Volume.....	129
Video Player Support	130
Video Player Control Panel.....	132
Replay Files.....	134
Recording Local Activity	134

Recording Replay Files At Client PCs	135
Watching Recorded Replay Files	136
Showing Replay Files to Clients	137
File Transfer	138
The File Transfer Window	138
Copying Files and Directories	140
To transfer files between Clients.....	142
Deleting Files and Directories.....	142
Creating Directories.....	142
Renaming Files	143
Changing File Attributes	143
Print File Transfer List.....	144
Synchronising Directories	145
Arranging multiple File Transfer Windows	145
Applying a filter to files in List View	146
Changing the View format in the File Transfer Window.....	146
Changing the sort orders in a File Transfer Window.....	147
File Distribution.....	148
The File Distribution Window.....	148
Distributing Files.....	149
File Manager	151
The File Manager Window.....	151
Managing Files on the Control workstation	152
Control/Client Chat Sessions	153
Disable Chat Sessions.....	157
Sending Messages to Clients	158
Dealing with Help Requests.....	159
Capturing a Client's printed output.....	161
Remote Clipboard	163
Integration With Explorer	165
Remote Command Prompt	167
Using the Client.....	168
The Client Main Window	169
Connecting to a Control	170
Disconnecting from a Control	171
Raising a Help Request	172
Chatting to a Control workstation	172
Receiving Messages from a Control workstation.....	173
Resetting the Client Video Driver on Windows 95/NT4	173
Configuring the Client	174
Configuring the Client	175

Editing or creating Configuration Files	177
Basic Client Configuration	180
Advanced Client Configuration	181
Connectivity Options	183
Set TCP/IP Connection	184
Set IPX connection	185
Set NetBIOS connection	186
Set HTTP connection	187
Dialin Bridge Settings	189
Advanced Setting	191
Web Extensions	192
Security Options	193
General Settings	193
Access Privileges (Basic)	195
Access Privileges (Advanced)	197
User Validation	200
User Acknowledgement Options	202
Connect Options	204
Disconnect Options	206
Protect Configuration Settings	208
File Transfer Settings	209
Replay File Settings	210
Event Logging	211
Remote Control Options	214
View Settings	214
Show Settings	217
Audio Settings	219
Client Interface Options	220
Client Settings	220
Help Request Settings	222
Customisable Text	224
Profile Options	225
Configuring the Control	226
Configuring the Control	227
Multiple Control Profiles	229
Adjusting Client Settings for a Control session	230
General Settings	231
Connectivity Options	232
Set TCP/IP Connection	232
Set IPX Connection	234
Set NetBIOS Connection	236
Set HTTP Connection	237

Remote Dialup Settings.....	238
Advanced Settings	240
Security Options.....	241
Security Settings	241
Event Logging	243
Replay Files.....	244
User Permissions	245
Startup Settings.....	246
Remote Control Settings.....	248
View Settings	248
Keyboard/Mouse Settings.....	252
Print Capture Settings.....	254
Audio Settings	257
Control Interface Settings.....	258
Interface Settings	258
Functions.....	261
Help Request Settings.....	263
File Transfer Settings	265
File Location Settings	268
NetSupport Protect – Switch Desktop Protection Off	270
Managing and Organising Clients	271
Add a new Client	272
Delete a Client	273
Renaming a Client	273
Setting Client Properties	275
Creating a New Group.....	276
Adding/Removing Clients in a Group	277
Setting Group Properties	278
Remote Communications.....	279
Remote Communications Overview	280
Optimising Remote Connections	280
Setting up Remote Communications.....	281
The NetSupport Bridge.....	282
Setting up a Modem.....	283
Using NetSupport Over A Null Modem (Serial) Cable.....	284
Using NetSupport over the Internet.....	287
ActiveX Control	288
ActiveX Control	289

Web Extensions.....	291
PCIA.X.CAB – Cabinet File	291
ActiveX Control – HTML Examples	292
NetSupport Scripting.....	294
NetSupport Scripting Overview	295
Starting the Script Editor	296
Creating a simple Script	296
Scheduling and Running a Script.....	297
Technical Reference	298
Unloading a NetSupport Client.....	299
Restarting a Client.....	299
Using Compression Effectively	300
Using Cache Effectively	300
Remote Client Hardware and Software Inventories	302
The Inventory Window	303
Using NetSupport's Security features effectively.....	308
Understanding IP Addresses.....	310
Understanding IPX Addresses.....	311
Using Command Line Instructions	312
Integration with Active Directory	315
Glossary	317
Readers Comments	328

Welcome to NetSupport

About this Manual

NetSupport Manager is designed to give IT managers, mobile professionals, telecommuters and trainers the power and flexibility to access and control a remote workstation from anywhere at anytime.

Dynamic screen handling combined with powerful file transfer and general communication requirements makes NetSupport the complete communications solution for remote control.

A connection can be made through another workstation, a telephone line, local area networks (LAN), dial-up networking, or using a local Internet Service Provider. A connection can also be made through a direct connection between two workstations using a serial cable.

This User Manual contains instructions for installing and running NetSupport Manager.

Conventions Used

The following logical and easy to understand conventions are used in this manual: -

- Step-by-step instructions, which should be performed in sequence, are shown as numbered paragraphs, beneath a clearly stated, 'How To Do' heading.
- As there is often more than one way of carrying out a task you will find 'Or' options also included.
- Additional tips or explanatory notes regarding these instructions are enclosed in a border under the heading 'Note'.
- Individual items in menu commands are enclosed in braces and should be followed in sequence, for example: {Client}{Broadcast}.

Terminology Used

Control	The workstation that is used to take over (remote control) another.
Client	The workstation that is to be taken over.
Available Client	When the NetSupport Client program has been installed on a workstation, it becomes available for connection by a Control. A Client must be available before a Control can connect to it.
Selected Client	Using the mouse you can select and highlight the Client or Clients to work with.
Connected Client	All available Clients or Groups of Clients can be chosen for simultaneous connection. A Control can only remote control a Client to which they are connected.
Known Clients	Having connected to Client machines, NetSupport stores a list of Clients in the Tree View, All Computers Folder. These are Known Clients.

About NetSupport

In this chapter ...

You will be introduced to the main features and benefits of NetSupport Manager.

What is NetSupport Manager?

Every organisation, whether large or small, depends in part on their IT infrastructure to remain competitive & efficient and to ensure static workers and mobile users maximise their productivity for the business.

It therefore follows that the IT Department is one of the most essential resources within a business entity and so supporting this function is critical to any success, whilst ensuring capital expenditure and associated costs are kept to a minimum.

Historically Remote Control software has been presented as the most efficient solution in improving the responsiveness of the helpdesk and support departments. Its largest single contribution being the tool that removes the need for support staff to physically visit a users PC to resolve technical issues.

The dual benefits of this are that users are presented with speedier response times and so the downtime of critical applications is reduced together with support staff being able to operate more efficiently as their resources are 'on hand' and not 'on the road' visiting users.

As with other areas of IT, remote control has evolved, with users looking for multi-tasking solutions and the associated economies of scale, where they can rely on a single box product to perform a whole range of functions, where traditionally this was handled by multiple software packages and vendors.

NetSupport Manager (NSM) is no exception to this evolution. Combining unrivalled remote control with innovative desktop management functionality, NSM offers one of the fastest ROI's on the market.

NetSupport Manager is available fully localised in English, French, Spanish, German, Italian, Japanese and Brazilian Portuguese.

Features

NetSupport Manager contains a wealth of features to assist you to Train, Support, Monitor and Manage Clients.

Remote Control

Watch, Share or Control the screen, keyboard and mouse of a Client irrespective of colour resolution, network protocol or operating system at either end.

Connectivity

- Dynamically find and list all Clients on the Network.
- Connect by Client name.
- Connect by Network address.
- Connect via a database of known Clients.
- Connect entire groups in one step.
- Client/Control connections via NetSupport's Internet Gateway providing seamless Remote Control between PCs that may both be located behind different firewalls.
- Connect to and remote control Linux and Pocket PC based systems.
- Connect to and remote control a Mac based system that has a previously installed VNC (virtual network computing) Client.

Message

Send a message to one or more chosen Clients, or even broadcast to all Clients on the network.

Chat

Conduct a text chat session in real time between the operator at the Control and one or more users. Annotate tools provide 'Whiteboard' capabilities.

File Transfer and Distribution

Transfer and manipulate files between workstations, using advanced 'Drag and Drop' technology. Includes support for Long File names, Remote File Edit, Delta File Transfer and more. Copy from a workstation to many workstations, distribute Software or Synchronise Directories. To ensure security while transferring files use encryption on all data being transferred.

View

View more than one Clients screen at the same time, or sit back and watch each connected screen in Scan Mode. The ability to record the activity on a Client workstation while it is remotely controlled, capture a Client's print output and cut and paste between workstation applications comes as standard.

Scan

Automatically cycle through each Client's workstation in turn, or scan multiple Clients simultaneously, displaying its screen on the Control workstation. This enables the Control to keep a discrete watch over what the Clients are running on their workstations. Particularly important with modern Internet access! The Control does not even need to be in the same room.

Monitor Mode

A convenient thumbnail view of each connected Client screen is displayed at the Control providing a quick and easy method for monitoring activity at remote PCs.

Show

Display the Control's screen on individual or multiple Clients or display a selected Client's screen to other Clients.

Remote Client Hardware/Software Inventory

Powerful hardware/software reporting combined with real-time status information for applications in memory, processes running and installed services provide all the key information needed to assist in speedy problem resolution. Over 50 items of information are collected specifically about the hardware or environment of the Client PC.

Launch Applications

Launch an application on one or all Client workstations at the press of a button.

Multimedia

NetSupport provides full Audio and Video Support.

Help Request

Clients can raise requests for help. The Control is instantly alerted to the Clients need for assistance via a pop up box, on their screen.

Power Management

Remotely logoff and shutdown Client workstations to minimise power consumption.

Scripting

NetSupport includes a powerful integrated Scripting Language and Scheduling Suite that enables you to make use of all of its functions in unattended mode.

Remote Communications

Take control of workstations on remote LANs/WANs or standalone workstations via Dial-up Modem (PSTN), ISDN, Internet or Direct Serial Link.

Web Browser Integration

Remote Control a workstation using ActiveX Control Web Browser. Using your Internet connection, download the 350k ActiveX Control software from your Company Website and remote control over IP on your office workstation. This is the ultimate, in portable Remote Control.

Desktop Integration with Explorer

NetSupport Manager integrates directly with explorer, allowing you to launch key functionality direct from your system without needing to first start NetSupport.

Comprehensive Security Features

Exceptional range of security options to meet all needs, including: -

- Password protection at Client and Control.
- User present acknowledgement required at Client.
- Connection Audit trail.
- Disable file transfer or specific files and directories.
- Limit Functionality depending on which workstation is connecting.
- Allow a Control to Watch only.
- Restrict file transfer to specific drives, directories and files.
- Dial-back to different numbers according to password.
- Restrict connections to named Controls.
- Customise Control and Client profiles to enable and disable virtually every feature depending on the security level of the signed on User.
- Set Unique Security Keys on both Control and Client.
- Integrates with existing NT profiles & Security.
- DES/AES Encryption

Easy to Install and Configure

- Install on Client workstations without the need to visit the individual machines using NetSupports Remote Deployment Utility.
- Silent Installation across the WAN.
- Central maintenance of Client Profiles.
- Configuration utility for Windows.
- Protocol Transparent Control, (use IPX, NetBIOS, TCP/IP and HTTP simultaneously).

Applications

NetSupport's wide range of features makes it an ideal tool for a wide range of applications. Some examples might include:

Help Desk

Use the remote control features to provide fast, cost effective support to end-Users in an Office or Help desk environment. Reduce the cost of providing support while improving productivity and the speed of problem resolution.

Telecommuting

Use the Remote Communications modules to enable staff to work from home, while having access to all the functionality on their office workstation.

Training

NetSupport's sophisticated Show functions provide the ideal demonstration tool. In addition, a full working copy of NetSupport's training package, NetSupport School, comes as standard, providing additional features ideally suited for the training environment.

System Automation

Use the powerful integrated scripting language to automate regular tasks such as uploading and downloading files.

Use the Launch Application function to set tasks running without end User intervention. Take advantage of the scheduler to save costs by running these tasks overnight.

Desktop Management

Use the combination of File Distribution and Scripting to manage User desktops and distribute software. Automatically retrieve workstation information such as Free Disk space.

Use the Registry Edit functions in Scripting to re-configure remote workstations.

User Management

Use the enhanced security features to configure utilities available at a Client.

Set up different profiles and access levels at both the Control and Client depending on the Users level of responsibility.

Maintain a Replay File to audit the activity of a Client workstation.

Installation

In this chapter ...

How to install the required NetSupport Manager components on your Windows based PCs.

Planning an Installation

Installing NetSupport is exceptionally easy. If you follow a few simple rules you should be up and running within a very short time.

The first step is to decide what functions you want to install on each workstation.

Do you want it to be a Control or a Client ?

Control To be able to control other workstations, install a Control, sometimes called a Viewer.

Client To be controlled by another workstation, install a Client, sometimes called a Host.

Will you want to run more advanced NetSupport features from the workstation such as **Scripting** and **Deploy** or use the machine as a **Gateway**? You can further customise your installation by including a full working copy of NetSupport's training tool, **NetSupport School**.

What network protocol do you use?

Decide what networking protocol you have available on the workstation. NetSupport supports **TCP/IP**, **IPX**, **NetBIOS** and **HTTP**.

While NetSupport is multi-protocol, which means that the same Control can connect to Clients running on different protocols, you must choose a default. You can change this later.

Note: By default, the Control will be configured to use TCP/IP. If you are using a different protocol, you must configure this the first time you start a Control.

You are now ready to install NetSupport Control and Client programs.

For details of how to install on:

Windows CE compatible devices, refer to Installing a NetSupport Client on Pocket PC Devices.

Linux machines, refer to Installing a NetSupport Client on Linux Platforms.

Note: NetSupport Manager provides support for Windows 64 bit on Intel EM64 and AMD64 platforms. The NetSupport Manager Windows Installer can be used to install the NetSupport 64bit Client, for further information please visit www.netsupportsoftware.com/support/

Starting the Installation

Insert the NetSupport CD.

The NetSupport welcome menu will automatically appear when you insert the CD. (If it does not, access the CD-ROM drive from your workstation and run SETUP.EXE.)

Notes:

- If you are upgrading Windows NT to Windows 2000/XP or 2000 to XP you must ensure that you de-install NetSupport Manager prior to upgrading the operating system. NetSupport Manager can then be re-installed once the operating system upgrade has been completed.
 - If you are installing to an NT/2000/XP workstation or server, make sure that you are logged in as an Administrator.
 - While performing the installation, Help can be accessed at various stages of the process if required.
-

Selecting a Set-up Type

Choose NetSupport Manager for the required language variant. This will start the install program.

NetSupport Manager Setup Program

The Setup program Welcome screen will appear.



Please read the information on the screen carefully, before proceeding with the installation.

Click Next to continue.

NetSupport Licence Agreement

The NetSupport License Agreement will be displayed. Please read the License Agreement carefully and select I Agree and click Next to continue.


If you reject the License Agreement, (I Disagree) click Cancel. NetSupport Manager will not be installed and you will be directed to Exit from the install program.

Licence Information

Enter your NetSupport Licence details as supplied with the product and click Next.

Existing Installation Detected


This screen will appear if a copy of NetSupport is already installed on the workstation.



- **Overwrite the existing installation.**
Overwrites the existing version of NetSupport, in the folder specified at the top of the screen. Existing configuration files, *.ini, *.nsm and *.scp, for example, containing details of Known Clients, Groups and Scripts, will be retained for continued use.
- **Install in a new folder and keep your existing settings.**
You may prefer to keep the existing installation in the folder specified at the top of the screen, and choose a different folder for the new installation. The existing configuration files will be copied to the new location.
- **Create a new installation.**
Installs the new version of NetSupport in the required folder but does not retain existing configuration files. If installing in a different folder, the existing version will remain on the workstation, you may want to manually delete these files after the workstation has restarted.

Select the required option and click Next.

Select Installation Type



Determine the components to install on each workstation by selecting one of the three available installation types.

- **Typical Installation**
Installs all the components that a Control User would generally need. Excludes the Gateway and NetSupport School components. See below for a description of each NetSupport Manager component.
- **Client Only**
Enables the workstation to be remote controlled.
- **Custom**
Enables you to individually select the mix of components that are appropriate for the workstation. Control and Client are selected by default but you can de-select either component if it is not required. See below for a description of each NetSupport Manager Component.

Destination Folder

By default, NetSupport will be installed in the folder **C:\Program Files\NetSupport Manager**.

Note: If an existing installation was detected, you may have chosen to install in a different folder. Click Browse to choose the required location.

Click Next to continue.

NetSupport Manager Components

If you have selected Typical Installation, all components, excluding Gateway and NetSupport School, are installed. If you have selected Custom, you can choose the components individually to suit the requirements of each workstation.

Client	Install this component on workstations you want to remote control.
Control	Install this component on workstations that will be taking control of Client workstations. It is recommended that the Client component is also installed in order to use the full range of NetSupport functions, for example Show.
Scripting	Install NetSupports integrated Scripting and Scheduling suite. Create scripts to automate manual tasks and schedule them to run at specific times. Ideal for overnight updates. See the NetSupport Scripting section of this manual for more information.
HelpFiles	Install on-line Helpfiles, providing information and guidance on all NetSupport functions and features.
Configurator	Client settings and security are established using the Client Configurator. Basic settings can be entered at the end of the installation process but to set more advanced options, install the Configurator component.
Remote Deployment Utilities (Supported on XP/NT/2000)	The Deploy Utility enables you to perform multiple NetSupport Manager installations without the need to visit each individual workstation. See the NetSupport Deploy section of this manual for more information.

Gateway

NetSupport's Gateway feature provides a means of connecting Clients and Controls across the Internet, thus delivering web based remote control without the need for modifications to existing Firewall configurations. There is no direct connection between the Client and Control, all data is passed via the Gateway. The Gateway component can therefore be installed independently of the Control and Client. If you choose to install the Gateway component, the Gateway Configuration dialog will appear after the installation has finished.

School Components


Installs NetSupport's training tool NetSupport School. If you choose to install the School components and the Control, NetSupport Tutor will be installed along with the Control component. Selecting the School and Client component will only install the NetSupport School Student component along with the Client.

Note: NetSupport provides exceptional multimedia support. The NetSupport Video Player enables you to run video files on Client workstations, enhancing training sessions and demonstrations. This component is installed by default.

If you do not want icons to be created for the selected components, un-check the **Create Icons For Selected Components** box.

Select Components

If you have chosen to perform a **Custom** Installation, you will be able to select the required components from the list provided.



Select the required components.

If you do not want icons to be created for the selected components, un-check the **Create Icons For Selected Components** box.

Click Next to continue.

Start Installation

To start the installation, click Next. To change any of the previous selections, click Back. To quit the installation, click Cancel.

Notes:

- If you have changed your Windows 2000 Local Security Policy Settings for unsigned driver installation behaviour, you may experience problems when running a NetSupport Client.
 - If you have elected to install a Client, Set-up will make the required amendments to your System.INI and or registry, to load the Client as Windows initialises. NetSupport will not replace any of your existing Drivers.
-

Installation Complete

This final screen confirms that the installation has been successful. You can choose to create a desktop icon for the Control.

Run Client Configurator

At the end of the installation process, you will have the opportunity to run the Client Configurator. This enables you to set basic Client information and security. If the Configurator is being installed as one of the selected components, you will be able to access more advanced configuration options.

Run Deploy

Selecting this option will run the NetSupport Deploy Utility after the installation process. This allows you remotely to install and configure NetSupport on multiple workstations.

Note: NetSupport can be fully integrated with Microsoft's Systems Management Server. If the NetSupport installation process detects the presence of the SMS Administration Console, you can decide whether to include the integration. If you select Yes, please refer to the README file 'SMS Integration.TXT' after the installation has completed for more information. The file can be found in the NetSupport Manager program folder.

Click Finish to exit the Setup program. Remove the CD and restart the workstation.

Note: If you chose to install the Gateway component, the Gateway Configuration dialog will appear. This primarily allows you to create a security key for the Gateway.

Uninstalling NetSupport

The standard method for uninstalling NetSupport is to select NetSupport Manager in Control Panel – Add/Remove Programs.

For Windows XP, 2000 and NT workstations, NetSupport Deploy can be used to perform multiple uninstalls from a remote location. Refer to the NetSupport Deploy section of this manual for more information.

Evaluation Kit

NetSupport Manager is available as an Evaluation Kit either from distributors or free as a downloaded copy off the Internet. This allows you to trial NetSupport before your purchase. The Evaluation Kit software is fully functional, apart from the following restrictions:

A maximum of five Clients can be active on the network simultaneously.

The Client and the Control programs will not run after the kit expiry date has passed.

Upon purchase, these restrictions are removed once serialisation has been completed. This process upgrades the Evaluation Kit into a fully licensed copy.

To upgrade an Evaluation Kit to a fully licensed copy

In the directory that you have installed the Program Manager Group 'NetSupport' open the file PCILIC.EXE.

The NetSupport Manager Licence dialog box will appear asking you to enter your licence details. Please note that all entries are cAsE sEnSiTiVe.

When you have entered the correct licence details click **GENERATE**. You now have a fully licensed copy of NetSupport Manager.

Advanced Installation

In this chapter.....

How to prepare and run 'silent' installations across a network;
Using the NetSupport Deploy utility to perform multiple installations;

Installing a NetSupport Client on Pocket PC devices;

Installing a NetSupport Client on Linux Platforms.

Creating an administrative (network) installation

An administrative installation (distribution copy) of NetSupport Manager is designed to assist administrators to install NetSupport on Networked PCs where the installation media or License details may not be readily available and it is anticipated that a number of installs will be performed either at once or over a period of time.

This type of installation can also be preconfigured to setup NetSupport Manager with certain options, therefore ensuring that all NetSupport installations are configured the same.

Once created, the distribution copy can be used when performing a Silent Installation or as part of a NetSupport Deploy routine.

To Setup a distribution copy of NetSupport on a Server

1. Create a folder on the network that is accessible to all PCs that you may want to install on.
2. Copy, from your original source media (CD or download) the file SETUP.EXE.
3. Create and copy a valid NSM.LIC file to this folder. If a License file is not present in the folder when running the install, NetSupport will be installed using the default Evaluation license.
4. Create and copy a CLIENT32.INI file to this folder.

Note: You can make the network folder 'read only' to avoid the configuration being altered by unauthorised users.

To Install NetSupport from a Server onto individual workstations

1. At the required workstation, navigate to the network folder containing the NetSupport Manager setup files.
2. Run Setup.exe.
3. Follow instructions on Starting the Installation.

Silent/Unattended Installations

On Windows XP, 2000 and NT, NetSupport Deploy enables you to pre-configure a NetSupport installation and remotely deploy it to multiple workstations. For Windows Me/98/95, and if required, XP, 2000 and NT, you can perform a similar 'Silent' Installation by editing and running the relevant files manually.

To perform a silent install


1. Create a distribution copy of NetSupport, see Creating an administrative (Network) installation, containing the required NetSupport installation files.
2. To determine the properties for the Installation, run INSTCFG.EXE from the NetSupport program folder. The Install Configuration Options dialog will appear. (See The Install Configuration Options dialog section below for a full description of this dialog) Your chosen properties are stored in a parameter file, default name Values.TXT.
3. Choose {File}{Save} and save the 'Values.TXT' file to the folder containing the distribution copy

Note: For the purpose of a Silent Install, you can save this file with a name of your choosing.

4. To perform the Silent Install at the required workstation, from the folder containing created above, run:
Setup.exe /s /m=values.txt. (where Values.TXT = the filename created in 3)

Install Configuration Options Dialog

When performing a Silent Installation or using NetSupport Deploy, you can customise the installation to suit individual requirements. This dialog, accessed by running INSTCFG.EXE from the NetSupport program folder if performing a Silent Installation or if using NetSupport Deploy, via the Install Properties General Tab, enables you to specify the properties for the installation. The information is stored in a parameter file, Values.TXT.



General

Install Directory

Specify the directory where NetSupport Manager will be installed. Leave blank to install in the default directory, \Program Files\Netsupport Manager.

Start Menu Folder

Specify a name for the program group or leave blank for NetSupport.

Restart Machine

Check this box to automatically Restart the Client workstations upon completion of the installation. The NetSupport Client does not become active until the workstation has been restarted.

Note: Leave the box un-checked if using NetSupport Deploy to perform the installation. Additional Restart options are available within the Deploy routine.

SMS Integration

NetSupport Manager can be fully integrated with Microsoft's Systems Management Server. If the SMS Administration Console is present on the Client machine, check this box to allow integration.


Client Parameters (Optional)

If you have created a particular Client Configuration file for use after the installation, specify the path and file name here. Depending on the location of the file, you may need to provide a set of User Credentials, name and password, to give Clients access to the file. In order to specify the parameters in the correct format, it is suggested that you create them in the NetSupport Client Configurator and copy them to this field.

Leave the field blank if you are installing from your distribution copy or if you want to use the default Configuration file contained in the NetSupport setup package.

To Specify Client Parameters

1. Open your NetSupport Manager Program Folder by choosing {Start}{Programs}{NetSupport}{NetSupport Configurator}.
2. Choose Advanced.
3. Select {Profiles}{Client Parameters} from the Configurator Drop Down Menu.
4. The Client Parameters dialog will appear.



5. Click Add to specify the parameters.

Notes:

- If User Credentials are required, they must precede the Configuration file name.
 - Each set of parameters must be added separately.
-
6. If required, enter the User Credentials (Username and password). Click Ok. The appropriate strings will appear in the dialog.
 7. Click Add to specify the location of the Configuration file. Click Ok.
 8. When the Client Parameters dialog contains the required strings, see example above, copy them individually to the Install Configuration Options dialog. (Use Ctrl C to copy, Ctrl V to Paste)

Icons

Leave the Icons box un-checked if you want to install an icon for each NetSupport Component. Check the required boxes to limit the number of icons created.

Components

Check the relevant boxes to indicate which NetSupport Components will be installed on the Client machines. See the 'Starting the Installation' section of this manual for a detailed description of each component.

Note: When selecting the School components, the installed component will depend on which Control or Client option is selected with this. If you choose to install the School components and the Control, NetSupport Tutor will be installed along with the Control component. Selecting the School and Client component will only install the NetSupport School Student component along with the Client.

NetSupport Deploy - NetSupports Remote Install Utility

The NetSupport Deploy Utility provides Network Administrators with the facility to install and configure NetSupport Manager on multiple workstations without the need to visit the machines individually.

You are provided with a view of your Network, allowing you to pick and choose which workstations you want to deploy to.

With NetSupport Deploy you can:

- Remotely Install a NetSupport package on multiple workstations simultaneously.
- Create and download specific Client Configurations to multiple workstations.
- Remotely update NetSupport License details on multiple workstations.
- Remotely Uninstall a NetSupport package from multiple workstations simultaneously.

Installing the Deploy Utility

When installing NetSupport, select Typical Installation to install the Deploy Utility automatically. Alternatively, you can also choose it as part of a custom installation.

Note: NetSupport Deploy is currently only supported on Windows XP, 2000 or NT workstations.

Planning

NetSupport Deploy is a powerful utility that makes installing NetSupport packages on multiple workstations a quick and easy process. However, while we endeavour to ensure that there are no limitations or incompatibility issues in the use of the software, it is recommended that a trial deploy is performed on a small number of workstations to ensure there are no conflicts with other similar products such as remote control or desktop security packages. In addition, for added security and protection you must have appropriate administrator rights for the machines you are deploying to.

Deploying on Windows XP

To enable you to deploy NetSupport on Windows XP Professional, you need access to the Admin\$ share on the remote machine in order to transfer the package to be deployed. By default there is no access allowed to Admin\$ share.

To enable Network access:

1. In Administrative Tools select Local Security Policy.
2. Select {Security Settings}{Local Policies}{Security Options}
3. Select {Network access : Sharing and security model for local accounts}
4. Alter the setting for this policy to {Classic – local users authenticate as themselves}

The Admin\$ share will now be available and you can deploy as normal.

If upgrading from Microsoft Windows XP Service Pack 1 to Service Pack 2, Windows Firewall will by default block all Network activity produced by NetSupport Manager. To enable NetSupport to function correctly we have provided a utility that will configure Windows Firewall.

To enable NetSupport Manager in the Windows Firewall Configuration


1. Download the ICFCONFIG.EXE File (link at www.netsupportsoftware.com/support/)
2. Run this utility on a machine with NetSupport Manager Installed using the following command
ICFCONFIG -e NSM
3. This will create all the required entries in the Windows Firewall Configuration to allow NetSupport Manager to function correctly.

The ICFCONFIG utility can also be used to remove a NetSupport Product from the Windows Firewall Configuration see our website at: www.netsupportsoftware.com/support/ for all the ICFCONFIG Command line options.

Starting NetSupport Deploy

1. Select NetSupport Deploy from your NetSupport Program Group.
2. The NetSupport Deploy Main Window will appear.

NetSupport Deploy Main Window



The Deploy Main Window is divided into the following sections:

Menu Bar

The Menu Bar contains a series of drop down menus that can be used to access the various tools and configuration utilities for the deploy process.

Left Hand Pane

Contains three tabs, Network, Log Files and Security.

Network and Security Tabs

List, in a Tree View, the available Networks, Domains and Workgroups that can be selected for a deploy routine.

Log Files Tab

Lists, in a Tree View, a history of previous deployments.

Right Hand Pane

With the **Network Tab** selected, you are provided with a range of general information, machine name and platform for example, about the workstations located on the selected Network/Domain.

The **Log Files Tab** provides a breakdown of past deployments categorised by type.

The **Security Tab** also lists information specific to each individual workstation located on the chosen Network/Domain. In addition to the machine name, you will be able to identify the IP Address, determine if the machine already has a NetSupport Client installed and which version is running, whether the Client is password protected or has User Acknowledgement set. With this information to hand you can decide in advance which machines to include or exclude from the forthcoming deployment. For example, if a current NetSupport Client is already installed at some of the workstations you might choose to ignore it.

Preparing a Deployment Routine

Choosing Who To Deploy To

1. From the Main Window select the Network or Security tab.
2. A list of available Networks, Domains and Workgroups will appear in the left hand pane. Expand or reduce the tree list by clicking on + or -.

Note: You can also deploy to specific IP Ranges by adding the appropriate address range to the tree. Select {Tools}{Add IP Domain} from the Menu Bar.

3. Highlight the required group.
4. The names of the workstations belonging to the selected group will appear in the right hand pane. You can change the appearance of the list view by selecting {View} from the Menu Bar.
5. Select the workstations to include in the deploy routine. (You can use CTRL-Click or SHIFT-Click). Before deciding to include or exclude a workstation, you can view its properties by right clicking on the machine name.

Choosing What To Deploy

You can choose:


- NetSupport Package.
- Client Configuration.
- NetSupport License File.
- Uninstall NetSupport.

Note: The properties for each of the above can also be pre-defined if it is not convenient to deploy immediately. See Pre-define settings for a future deployment.

Deploy a NetSupport Package


A NetSupport Package is created as standard when the Deploy component is selected with the installation. To distribute the package select the required workstations:

1. Choose {Deploy}{NetSupport Package} from the Deploy Main Window Drop Down Menu.
or ,
Right click on the selected workstations and choose Deploy-NetSupport Package.
2. The Deploy Summary dialog will appear.



This dialog provides a summary of the options you have selected for the deployment. Click Properties to amend the information for the deployment.

3. The Install Properties dialog will appear.



4. To amend the properties for the deployment select the relevant tab.

General tab

Used to specify the NetSupport package to deploy and which components are to be installed.

The description for the package will be set to NetSupport Manager.

By default the location of the package to be installed is set to the Deploy folder where the NetSupport Manager package has been created.

Click Edit to specify the components to install. The Install Configuration Options dialog will appear. (See the 'Install Configuration Options Dialog' section of this manual for a full description of this dialog.)

Note: Because of the way NetSupport Deploy handles restarting workstations, leave the Restart Machine box un-checked. This is only relevant when performing a Silent Install where The Install Configuration Options dialog is also used for specifying the options to install.

When you have completed this dialog choose {File}{Save} to save the Values .TXT file to the folder containing the distribution copy of NetSupport.

Choose {File}{Exit} to return to the Install Properties dialog.

Options Tab

Use the information supplied in the Network and Security tabs to identify which machines may already have NetSupport installed, you can then choose to:

- Ignore them by checking the Skip machines already running NetSupport box.
- Update the machines with the latest version by checking the Update new or older systems to current version box.
- After deploying the package, you can confirm that the Client is running by checking the Verify Client running after restarting box. Ensure that workstations are restarted automatically after the deploy for this option to work. See Restart tab.

Acknowledgement Tab

Consider whether the workstations will be in use when commencing the deploy. You can choose to:

- Install NetSupport Immediately. No prompt will be received at the workstations being deployed to.
- Warn user before installing NetSupport. The user will receive a prompt and needs to click OK for the install to commence. Users cannot cancel this.
- User can postpone NetSupport installation. You can specify the number of times a user can postpone the installation. If the user does choose to postpone, they will be re-prompted at hourly intervals or the next time they restart the workstation whichever comes earlier.

Message Tab


You can specify a custom message to be displayed at each workstation while the installation is in progress.

Restart Tab

These options are only applicable if the target PCs require a forced restart to complete the installation.

- Advise user to restart machine. At the completion of the deployment, a message will be displayed at workstations asking the user to restart the PC at the next convenient opportunity. Do not choose if above Note applies.

- Insist user restarts machine. A message will be displayed at workstations, advising the user to restart the PC to complete the installation.
 - Force restart. At the end of the deployment, a message is displayed advising users that the workstation will be restarted. A time bar is displayed indicating how many seconds it is before the restart commences.
 - Automatic restart if not logged on. If the workstation being deployed to is not logged on, restart will commence automatically.
5. Click OK to return to the Deploy Summary dialog.
 6. Click Deploy to commence the installation. A progress dialog will appear, enabling you to monitor the deployment as it installs on each workstation.



The dialog has two tabs:

Log tab enables you to monitor the deployment as it reaches each workstation.

Status tab lists the stage the deployment has reached on each workstation. For example, the installation may be complete on one machine but still in progress on another.

7. Click Close to return to the Deploy Main Window when the installation is complete.

Deploy a Client Configuration

Using NetSupport Deploy, you can remotely deploy a Client Configuration file containing specific Client settings. For more information on Configuring Clients see the Configuring the Client section of this manual.

1. Select the required workstations.
2. Choose {Deploy}{Client Configuration} from the Deploy Main Window Drop Down Menu.
or,
Right click on the selected workstations and choose Deploy-Client Configuration.
3. The Deploy Summary dialog will appear.
4. Click Properties to enter the details for the deployment.
5. Click Browse to specify the folder containing the Client Configuration file that is to be deployed. The default configuration file is CLIENT32.INI and is stored in the NetSupport Manager installation directory.
6. Click Edit to access the Advanced Client Configurator in order to make changes to the Configuration file. See the Advanced Client Configuration section of this manual for more information.
7. You can specify additional Client parameters if required. For example, this may be the location of an additional Configuration file to which you want to add specific user credentials (Name and password).
8. For the new settings to take effect immediately, by default the Client Service will be automatically restarted after the deployment. If not required, uncheck the Restart the NetSupport Client service box.
9. Click OK to return to the Summary dialog. You can view the contents of the configuration file by clicking on the file name.
10. Click Deploy. A progress dialog will appear enabling you to monitor the status of the deployment.
11. Click Close when complete.

Deploy a NetSupport License file


When installing a NetSupport package, a license file is sent to each workstation. However, there may be occasions when the license information needs updating. For example, you have purchased additional licenses and the license file needs updating to reflect this. By using NetSupport Deploy you can remotely update the file on user workstations.

1. Select the required workstations.
2. Choose {Deploy}{NetSupport License file} from the Deploy Main Window Drop Down Menu.
or,
Right click on the selected workstations and choose Deploy-NetSupport License file.
3. The Deploy Summary dialog will appear.
4. Click Properties to enter the details for the deployment.
5. Click Browse to specify the folder containing the license file that is to be deployed. The default file is NSM.LIC.
6. For the new settings to take effect immediately, by default the Client Service will be automatically restarted after the deployment. If not required, uncheck the Restart the NetSupport Client service box.
7. Click OK to return to the Summary dialog. You can view the contents of the license file by clicking on the file name.
8. Click Deploy. A progress dialog will appear enabling you to monitor the status of the deployment.
9. Click Close when complete.

Remote Uninstall

Using NetSupport Deploy you can remotely uninstall a NetSupport package.

1. Select the required workstations.
2. Choose {Deploy}{Uninstall NetSupport} from the Deploy Main Window Drop Down Menu.
or,
Right click on the selected workstations and choose Deploy-Uninstall NetSupport.
3. The Deploy Summary dialog will appear.
4. Click Properties to enter the details for the deployment. The Uninstall NetSupport dialog will appear.



5. Enter the properties for the deployment by selecting the four tabs in turn.

General tab

Provides a description of the package being uninstalled.

Acknowledgement Tab

Consider whether the workstations will be in use when commencing the deploy. You can choose to:

- Uninstall NetSupport Immediately. No prompt will be received at the workstations being deployed to.

- Warn user before uninstalling NetSupport. The user will receive a prompt and needs to click OK for the uninstall to commence. Users cannot cancel this.
- User can postpone uninstall of NetSupport. You can specify the number of times a user can postpone the uninstall. If the user does choose to postpone, they will be prompted the next time they restart the workstation.

Message Tab

You can specify a custom message to be displayed at each workstation while the uninstall is in progress.

Restart Tab

To completely remove all NetSupport files, the workstations must be restarted.

- Insist user restarts machine. A message will be displayed at workstations, advising the user to restart the PC to complete the process.
 - Force restart. At the end of the deployment, a message is displayed advising users that the workstation will be restarted. A time bar is displayed indicating how many seconds it is before the restart commences.
 - Automatic restart if not logged in. If the workstation being deployed to is not logged in, restart will commence automatically.
6. When you have completed all four tabs, click OK to return to the Deploy Summary dialog. You can review your selections and edit if required.
 7. Click Deploy to commence the uninstall. A progress dialog will appear, enabling you to monitor the deployment as it uninstalls each workstation.
 8. Click Close when complete.

Pre-Define Settings For A Future Deployment

There may be occasions when you want to defer a deployment until a more convenient time of the day. With NetSupport Deploy you can prepare the settings in advance and choose when to perform the deployment.

Note: You select the workstations to deploy to when you are ready to run the deployment.

To Prepare The Settings For A Future Deployment

1. Choose {Deploy}{Configuration} from the Deploy Main Window drop down Menu.
2. The Deploy List dialog will appear. Select the required Deploy Option. (Package, Client Configuration, License File or Uninstall)
3. Click Properties and enter the required settings.
4. When all settings are entered, click Close to return to the Deploy Main Window.

To Run The Deployment


1. Select the workstations to Deploy to. See Preparing a Deployment.
2. Choose {Deploy} from the Main Window Drop Down Menu.
or
Right click on the selected workstations and choose Deploy.
3. Select the required Deploy option.
4. The Deploy Summary dialog will appear, showing your pre defined selections. You can edit these if required.
5. Click Deploy to start the deployment.

Log Files

When using NetSupport Deploy, information about each deployment, whether a package install, license update, configuration download or uninstall, is recorded. This provides a useful reminder each time you use the utility of what you have previously deployed. The information is stored in a Log File.

To view Log Files

1. From the NetSupport Deploy Main Window, select the Log Files tab.



2. In the left hand pane of the Main Window, increase or decrease the Tree View to see a description of each type of deployment, the date and time the deployment took place and the workstations that were deployed to.
3. As you select an item from the left hand pane, itemised information about that deployment will appear in the right hand pane.

Printing a Log File

1. Select the required Log File in the Tree View.
2. Choose {Log}{Print} from the Deploy Main Window Drop Down Menu.


Deleting a Log File

1. Select the required Log File in the Tree View.
2. Choose {Log}{Delete} from the Deploy Main Window Drop Down Menu.

Installing a NetSupport Client on Pocket PC Devices

Support for Windows CE compatible devices is provided, enabling installation of a NetSupport Client on Pocket PCs. A NetSupport Manager Control can then connect in the usual manner and perform a range of remote control tasks such as Chat, Message and File Transfer.

Note: If required, a NetSupport Manager Control can be installed on a Pocket device. For full installation instructions refer to our download site at www.netsupportsoftware.com.



An MSI Installer can be used with Microsoft™ ActiveSync to install the Client on a Pocket PC Device that has WiFi wireless LAN capabilities.

1. Before installing NetSupport Manager for CE ensure that the basic pre-requisites for your Pocket PC are in place. A relationship between your Control PC and the hand held device should be available and ActiveSync should be running.
2. With your Pocket device connected to the Control PC, run NetSupport's CE Installer. This is a downloadable utility. Please visit our downloads area at www.netsupportsoftware.com.
3. The installer will detect the pocket device and install a NetSupport Manager CE Client. The usual Client icon will appear in the system tray. The CE Client Configurator utility will be installed at the Control PC in Program Files. The Pocket PC must be connected to the Control in order to configure the Client options.

4. With the Client installed, the Control can connect and open a standard view session.

For information on currently supported features please visit,
www.netsupportmanager.com/mobile.asp

Installing a NetSupport Client on Linux Platforms

A NetSupport Client can be installed on Linux platforms, designed to run on a Windows manager, enabling a Control to connect, view the screen of the remote user and perform a variety of remote control tasks.

Note: NetSupport currently supports the following Linux Distributions: Red Hat, Fedora, SuSE.

1. A downloadable ZIP file containing the installation script and program files is available from our downloads area at www.netsupportsoftware.com. (Full installation instructions will also be available here)
2. Download to a directory on the Linux machine.
3. Extract the TAR BALL. A sub-directory called Install will be created.
4. Point to the directory and run the installation. (As a Root User)
5. The NetSupport Client will install to /usr/nsm, providing a Linux daemon.

At the NetSupport Control connect to the Client in the usual manner.

Note: When installing SuSE 9.3 and SuSE 10 distributions, the following error message will appear, "SuSEFirewall2: Warning: iptables does not support state matching. Extended IPv6 support disabled" this is a standard message and should be ignored.

For information on currently supported features please visit, www.netsupportmanager.com/linux.asp

Using the Control

In this chapter ...

You will discover how to use the wealth of features available to a Control User. From how to initiate a remote control session to how you then monitor and manage activity at the end-users desktop.

Starting the NetSupport Control

To start the NetSupport Manager Control program

1. Double click on the NetSupport Control icon in your NetSupport Program Group.
Or,
Choose {Start}{Programs}{NetSupport}{NetSupport Control} from your operating system.


As NetSupport Manager initialises, you will see a window in the middle of your screen with the NetSupport logo and version information. This only appears for a few seconds while NetSupport loads, after which, the Control Window will be displayed.

Note: By default, the Control is configured to support the TCP/IP protocol, however, it can support multiple protocols simultaneously. If you receive a protocol error message when starting the Control or want to configure it to support Clients running on different protocols select {Network}{Configure – Connectivity} from the Control Window drop down menu.

The Control Window

The Control Window is the primary interface for: -

- Configuring the Control;
- Connecting to Clients;
- Maintaining Client information;
- Selecting which Clients to work with;
- Selecting tasks to carry out.



The Title Bar

This indicates that you are in the Control Window and displays the name of the NetSupport Control workstation.

The Menu Bar

The Menu Bar contains a series of drop down menus that can be used to access the various tools and configuration utilities. These menus can also be used for connecting to and selecting Clients to work with as well as maintaining and organising Clients into work groups.

The Toolbar

The Toolbar contains shortcuts to the most frequently used tasks and tools. Options of a similar nature are grouped within the same icon. You can also add or remove icons to suit your personal preferences. See *Customising The Toolbar*.



The Quick View Bar

The Quick View Bar is used to switch between currently connected Clients. Clicking on the button containing the required Clients name brings that Clients View Window to the foreground.

The Quick Execute Bar

The Quick Execute Bar enables you to execute a previously saved application to a Client, without having to direct your way through the drop down menu. By clicking on the button containing the required application, you immediately execute it on the selected Client or Group.

The Thumbnail Toolbar






























The Thumbnail Toolbar provides quick and easy access to a convenient thumbnail view of each connected Client screen and allows you to amend the thumbnail settings.

The Tree View

The Tree View provides an explorer like structure for creating, displaying and organising NetSupport objects such as Clients and Groups.

The List View

The List View displays the contents of the currently selected Folder in the Tree View. You can switch the display mode between large and small icons, detailed view or thumbnail view. The information within the List View can be customised to show specific information relevant to you.

 All Computers All available computers		<table><tr><th>Name</th><th>User Name</th><th>Status</th><th>Description</th><th>Tran...</th><th>Address</th><th>Client Platform</th></tr><tr><td colspan="7">New Client</td></tr><tr><td> TEST30</td><td></td><td>Excluded</td><td></td><td>TCP/IP</td><td>>10.0.1.62:5405 (test30)</td><td>Windows 2000</td></tr><tr><td> TEST29</td><td></td><td>Local</td><td></td><td>TCP/IP</td><td>>10.0.1.63:5405 (test29)</td><td>Windows 2000</td></tr><tr><td> TEST22</td><td>testing</td><td>Connected</td><td></td><td>TCP/IP</td><td>>10.0.1.86:5405 (test22)</td><td>Windows XP</td></tr><tr><td> INWH298</td><td>pcigne</td><td>Local</td><td></td><td>TCP/IP</td><td>>10.0.0.13:5405 (invh298)</td><td></td></tr><tr><td> INWH309</td><td>NSLJON</td><td>Local</td><td></td><td>TCP/IP</td><td>>10.0.0.224:5405 (invh309)</td><td></td></tr><tr><td> INWH327</td><td>PCINJAU</td><td>Local</td><td></td><td>TCP/IP</td><td>>10.0.0.22:5405 (INWH327)</td><td></td></tr><tr><td> INWH330</td><td>pdajk</td><td>Local</td><td></td><td>TCP/IP</td><td>>10.0.1.73:5405 (INWH330)</td><td></td></tr></table>							Name	User Name	Status	Description	Tran...	Address	Client Platform	New Client							 TEST30		Excluded		TCP/IP	>10.0.1.62:5405 (test30)	Windows 2000	 TEST29		Local		TCP/IP	>10.0.1.63:5405 (test29)	Windows 2000	 TEST22	testing	Connected		TCP/IP	>10.0.1.86:5405 (test22)	Windows XP	 INWH298	pcigne	Local		TCP/IP	>10.0.0.13:5405 (invh298)		 INWH309	NSLJON	Local		TCP/IP	>10.0.0.224:5405 (invh309)		 INWH327	PCINJAU	Local		TCP/IP	>10.0.0.22:5405 (INWH327)		 INWH330	pdajk	Local		TCP/IP	>10.0.1.73:5405 (INWH330)	
Name	User Name	Status	Description	Tran...	Address	Client Platform																																																																	
New Client																																																																							
 TEST30		Excluded		TCP/IP	>10.0.1.62:5405 (test30)	Windows 2000																																																																	
 TEST29		Local		TCP/IP	>10.0.1.63:5405 (test29)	Windows 2000																																																																	
 TEST22	testing	Connected		TCP/IP	>10.0.1.86:5405 (test22)	Windows XP																																																																	
 INWH298	pcigne	Local		TCP/IP	>10.0.0.13:5405 (invh298)																																																																		
 INWH309	NSLJON	Local		TCP/IP	>10.0.0.224:5405 (invh309)																																																																		
 INWH327	PCINJAU	Local		TCP/IP	>10.0.0.22:5405 (INWH327)																																																																		
 INWH330	pdajk	Local		TCP/IP	>10.0.1.73:5405 (INWH330)																																																																		
 Browse Browse network for computers																																																																							
 Active Shows all connected computers																																																																							
 Help Requests Help Requests																																																																							
 Remote Networks Computers located on remote networks																																																																							
 Internet Gateways Computers available over the Internet																																																																							
 New York																																																																							
 Automation Automate common tasks on computers																																																																							

The Status Bar

The Control Status Bar is displayed at the bottom of the Control Window. It shows the current Status of the Control, the number of currently connected Clients and the number of items in the Folder. During a dialup connection it will also show communications details.


You can Hide or Display the Status Bar from the View Menu options on the Control Window drop down menu bar.

Customising the Toolbar

To enable you to customise NetSupport to your exact requirements, a variety of User Interface customisation features are available. One of these is the ability to set which icons you want to display on the Control Toolbar.

To customise the Toolbar

1. Choose {View}{Toolbar}{Customise} from the Control Window drop down menus.
2. The Customise Toolbar dialog will appear.



The two lists you can see contain the buttons that can be added to the Toolbar and those already on the Toolbar. To group the buttons together you can place separators between them.

Available Buttons

Displays a list of all the buttons that can be added to your Toolbar. This list shows the icon and the associated text that will be added.

Current Buttons

Displays the current buttons on your Toolbar. Separators are shown as a horizontal broken line. You can add a separator by selecting the item in this list to insert after and pressing the Separator >> button.

Add >>

Choose an item from the **Available Buttons** and select the position for this item in the **Current Buttons** list. The item is inserted after the selected item when you press the Add button.

Separator >>

Press this button to insert a separator into the **Current buttons** list after the selected item. Separators are used to visually group buttons together.

<< Remove

Choose an item from the **Current button** list to remove and then press this button. The item will be added to your **Available buttons** list unless it is a separator in which case it is just removed.

Reset

Pressing this button restores the **Current button** list to the defaults provided by the User Interface.









Press this button to move the selected Toolbar button up one position in the **Current button** list.

Press this button to move the selected Toolbar button down one position in the **Current button** list.

NetSupport Manager Control Toolbar Buttons

The appearance of a green arrow on some of the buttons indicates that a number of related tasks can be accessed via the icon.

The following icons are set by default.

Button	Name	Function
	New	Create a new Client, Group, Remote Network, Script Object, or Gateway.
	Connect	Connect to the selected Client or Group of Clients.
	Disconnect	Disconnect from the selected Client or Group of Clients.
	Browse	Search the Network for available Clients.
	Desktop	Perform a variety of Remote Control tasks. View Client screens, Show the Control screen to Clients, Scan Client screens, Playback or Record Replay Files.
	File	Access the various File/Folder Management options. File Transfer, Distribution and Manager.
	Actions	Perform a number of remote operations at the selected Clients. Launch the Remote Command Prompt, display a hardware/software Inventory, Chat with the Clients, Send a Message and Execute a program at the Clients.
	Manage	Manage the selected Client PCs. Reboot, Logout, Send Ctrl-Alt-Del, Power On and Power Off the Client PCs.



Properties

Display the Properties for the selected Client or Group.



Settings

Change the Settings for the current Configuration.

These buttons can be added to the toolbar as and when required:

Button

Name

Function



Add to Group

Add the selected Client to a new or existing Group.



Announce

Send an Announcement to the selected Client(s).



Available

This Control is available to receive Help Request connections.



Chat

Chat with the selected Client.



Configurations

Manage your Configuration Profiles.



Dial

Dial a Remote Network.



Disconnect All

Disconnect from all currently connected Clients.



Execute

Execute a program at the selected Client(s).



File Distribution

Display the File Distribution Window to the selected Clients.



File Manager

Display the File Manager Window for the Control Workstation.



File Transfer

Display the File Transfer Window for the selected Client(s).



Inventory

Retrieve a hardware / software inventory for the selected Client machine.



Logout

Logout the selected Client.



Message

Send a Message to the selected Client(s).



Playback

Play back a previously recorded Client session.



Power Off

Power Off the selected Client PCs.



Power On

Power On the selected Client PCs.



Quick Connect

Quickly connect to a Client by supplying its name or address.



Reboot

Reboot the selected Client.



Remote Command

Load the Remote Command prompt window.



Run

Run the selected Script.



Scan

Scan through connected Clients screens.



Show

Show your screen to the selected Client(s).



Tools

Manage and Execute User Defined Tools.




View Client


View the selected Clients screen.

The Control Window – Tree View

The Tree View is the access point for information about the various NetSupport Objects. An object may be an individual Client, a Group or even a collection of Help Requests generated by Clients. Each set of objects is stored in its own folder, as displayed in the Tree View, in the Control Window.



The individual objects in a Folder are displayed in the adjacent List View. For example, selecting the Active Folder will result in the List View changing to display all currently connected Clients.



The Tree can be expanded or contracted depending on the detail you require, by clicking your mouse pointer on the relevant icons to the left of a heading.

The available Folders are:**All Computers**

A list of all Known Clients that have been connected either during the current or previous sessions. It is very quick and easy to connect to a Client from this folder as it removes the need to first perform a Browse or know the network address of the Client.

Selecting the drop down arrow next to All Computers will show any Groups that have been created.

You can organise individual Clients into Groups. Once a Client is included in a Group, the entire Group can be connected and worked on simultaneously without the need to connect and select them individually.

Browse

This is a list of Clients discovered by running a Browse action in the current session. Connecting to a Client from this folder causes its details to be stored for later use in the All Computers folder.

Active

Any Client that is currently connected will be displayed in this Folder.

Help Requests

NetSupport includes a function at the Client that enables the Client User to send a request for help. A Control can be notified that it has received a Help Request from a Client in a variety of ways. If a Control is configured to receive all Help Request messages, the Control will be immediately notified, as the Help Request folder turns blue, it may even receive an audible beep. To alter the way in which a Control is notified of a Help Request and when it is available to receive them adjust the Help Request Tab in the Control Configurator.

Remote Networks

This refers to Clients that have to be connected over a dialup link. They may be Clients on a LAN in another building or even standalone workstations. In either event they are referred to as Remote Networks and the information concerning the telephone number to dial and the type of connection are stored in this folder.

Internet Gateways

The primary role of a NetSupport Gateway is to facilitate seamless Remote Control between PC's that may both be located behind different firewalls.

The Gateway provides a stable and secure method for locating Clients via http and delivers web-based remote control without the need for modifications to existing Firewall configurations.

Automation

Scripts created using the NetSupport Script Editor can be added to this folder. List View shows the names of each script and enables you to add new scripts to the list.

The Control Window – List View


The List View displays the objects stored in the corresponding Folder in the Tree View. For example, if you select the Active Folder, then the List View will contain the details of the currently connected Clients. Similarly, if you perform a Browse action the results of that Browse will be displayed.

By choosing {View} from the Control Window drop down menu, or right-clicking in the List View, you can change the appearance of the displayed items. The available options are Large Icons, Small Icons, List, Details and Thumbnail.

With Details selected you can tailor the information that is displayed about each Client.

To customise the List View

1. Select {View}{Columns} from the Control Window drop down menu.
2. The Columns dialog will appear.



The Tabs shown at the top of the List View relate to each of the Client List windows that are available for the Control.

Select the desired Tab, the left-hand window highlights columns that are available for inclusion, the right hand window shows those already included. Simply select the column name you require and then 'Add' or 'Remove'.

The Arrows to the far right of the window are used to adjust the order in which each column is displayed; the higher up the list represents position from the Left.

Finding Clients

Before you can open a View Window for remote control or file work with a Client or Clients, you must first connect to them.

Rather than having to know all the Client names and their network addresses in advance, NetSupport Manger provides a Browse facility that enables you to auto-discover them.

When you run a Browse action, the Control sends a message on all protocols for which it has been configured, asking all Clients to “sign-in” with their name, network address and protocol.


The responses are added to the Browse folder in the Tree View and their details are displayed in the List View. You can then connect and work with these Clients directly or organise them into groups for later use.

Once you have connected to a Client discovered by the Browse function, its details are automatically stored in the All Computers Folder in the Tree View. These Clients then become Known Clients and you can subsequently connect to them without the need to run a Browse action first.

Note: You may be using NetSupport's Gateway facility to establish Client connections, in which case you can choose to include Gateway Clients when Browsing. Although these will appear in the Browse folder along with any Network Clients they are not stored in the Known Client list.

To find a Client on a network

1. Choose {Network}{Browse} from the Control Window drop down menu.
Or,
Click on the Browse icon on the Control Window Toolbar.
Or,
Select the Browse Folder in the Control Tree View and click on the “Look for Clients” icon in the List View.
2. The Browse dialog will appear.



Enter a partial Client name or leave blank for all Clients

Type in the first part of a Client name here to narrow the search. If you have many Clients on your network, you may only be interested in those that begin with a certain word or letter. If you have Clients that begin with ADMIN, typing this in would return Clients such as ADMIN1, ADMIN_OFFICE and ADMINISTRATOR. To find all available Clients leave this field empty.


Only Clients Requesting Help

Select this check box to browse only for Clients that have requested help.

Include Gateway Clients

Check this box to include Gateway Clients when Browsing.

Click OK to begin the browse. An information box will advise you that the Control is browsing for Clients.



Press Cancel to abort your browse for Clients. This will take a few seconds, after which, a list of Available Clients on the Network meeting the criteria will be displayed in the Browse folder. You can then right click on individual Clients to connect to them, display their properties or carry out tasks.

If the expected Clients are not found it may be because NetSupport has not been configured to browse the required Networks. **See** 'Configuring The NetSupport Control For Subnet Browsing' for more information.

Connecting to Clients

Before you can remote control a Client, you must first connect to it.

To connect to Clients

1. Select the Client you want to connect to in the All Computers or Browse Folders and choose {Client}{Connect}.


Or,

Right click on the Client icon and choose {Connect}.

Or,

Double click on the Client icon to connect and View it immediately.

If the Client has been configured with security passwords you will be prompted to enter your USERID and the correct Password. This must be equal to the USERID and Password that has been set in the Clients Profiles.




Quick Connect

Quick Connect allows you to directly connect to a Known Client by **Client Name**, **Logged In User Name**, or by **Network Address** saving you having to perform a network browse and then selecting the desired Client from the List View.

Clients configured for HTTP connections through a NetSupport Gateway can also be selected.

To directly connect to Clients

1. Choose {Client}{Quick Connect} from the drop down menu.
2. The Quick Connect dialog will be displayed.



3. Choose the required connection method, Client name, Logged In User Name, or Network Address and Protocol.

Note: If the Client is configured for HTTP connections through a Gateway, in addition to the Name or User Name of the Client you will need to choose the appropriate Gateway name from the list provided.

4. Click Connect.
5. A dialog box will inform you that NetSupport is trying to connect to the named Client.

If the connection attempt is successful the Active folder will be opened and the Client Details displayed in the Client Status. You can then View it or conduct other one to one or group tasks.

Notes

- If you are using TCP/IP the address is in the form >192.168.100.20.
 - If connecting by User Name and more than one Client machine matches this criteria, a list of Clients will appear for you to select from.
 - If you are using the IPX network transport, the address is in the form >000001-12345678.
 - If you are using NetBIOS, the Client PC's address is the registered NetBIOS network name of that PC.
-

Connecting to Clients on different Protocols

NetSupport supports connecting to Clients on multiple transports. The four supported transports are IPX, TCP/IP, NetBIOS and HTTP. Within NetBIOS there are 8 logical adapters.

Transports can be configured and tested within the Connectivity option of the Basic or Advanced Client Configurator.

When the Control performs a Browse it looks over all configured transports. Highlight the desired Client and select Connect from the Client menu.

Connected Clients on different transports happily coexist within the Control. Operations such as File Distribution, Show and Scan work over different transports.

If you know that you only have Clients on one particular transport then the Control will initialise slightly quicker if you only configure it for this transport.

Configuring The NetSupport Control For Subnet Browsing

Most corporate networks are made up of a number of small networks that are connected together in order to provide end users with access to network resources. NetSupport Manager incorporates features that allow a NetSupport Manager installation on one network to be used to remotely manage computers on another interconnected network.

Using NetSupport Manager in its default configuration will enable you to remotely manage computers on a remote LAN if connectivity to that remote LAN is provided by a WAN.

However there are some configuration changes that are required to allow a NetSupport Manager Control to browse for Clients on remote LAN's. The configuration changes required are dependant on the network transport that you will be using with NetSupport Manager. The two most common transports that are used over WAN's are TCP/IP and IPX.


Configuring the NetSupport Manager Control for IP Subnet Browsing

Before configuring NetSupport Manager to browse on a remote IP subnet it is useful to understand how IP addresses are made up and in particular what an IP Broadcast Address is. See '**Understanding IP Addresses**' in the Technical Reference section of this manual for more information.

To Configure the NetSupport Control to browse IP subnets

1. Select {Network}{Configure} from the Control Window drop down menu.
or
To edit a Named Configuration file, choose {Tools}{Configurations} from the Control Window drop down menu. Select the required file and click Connectivity and Startup Settings.
2. Select Connectivity-TCP/IP. In the Browsing area click Settings.
3. The Configure TCP/IP Client Browsing dialog will appear.


4. Click Add and enter the Broadcast Address of the Network you wish to browse if known.



The dialog box titled "Enter IP Browse Address" has a blue header bar with a close button (X) on the right. It contains a text input field with the value "10.0.2.255". Below the input field are three buttons: "OK", "Cancel", and "Advanced >>".

or

To enable NetSupport to calculate the Broadcast Address, click Advanced and enter a Target IP Address followed by the Subnet mask or enter the required Address Range.



The dialog box titled "Enter IP Browse Address (Advanced)" has a blue header bar with a close button (X) on the right. It contains three radio button options: "Subnet" (selected), "Address Range", and "Terminal Services".
 Under "Subnet", there are two text input fields: "Target IP address:" with the value "10.0.2.10" and "Subnet mask:" with the value "255".
 Under "Address Range", there are two text input fields: "Base IP address:" and "No. of clients:".
 Under "Terminal Services", there are two text input fields: "IP address:" and "Port range:" with a "to" label between them.
 At the bottom are three buttons: "OK", "Cancel", and "<< Advanced".

5. Click OK.

Notes:

- When adding the address of a remote subnet, you must ensure that the broadcast address for the local subnet is also present. If not, the Control will not find any local clients when you perform a browse.
 - Some network Routers will suppress broadcast packets from being transmitted across WAN links. If this is the case then even if the Control is correctly configured you will not be able to browse the remote subnet.
-

Configuring the NetSupport Manager Control to Browse Remote IPX Networks

Before configuring a NetSupport Control to browse a remote IPX network it is useful to understand how IPX addresses are formatted. You will need to have the IPX network numbers for each IPX network that you wish NetSupport Manager to browse, this includes the IPX network number for the local network on which the NetSupport Manager Control is installed. See '**Understanding IPX Addresses**' in the Technical Reference section of this manual for more information.

To Configure the NetSupport Control to Browse Remote IPX Networks

1. Choose {Tools}{Configurations} from the Control Window drop down menu.
2. Select the required Configuration file and click Connectivity and Startup Settings.
3. Select Connectivity-IPX.
4. Check the Use IPX and Record Clients' Network Numbers options.
5. In the Use Networks box enter each of the IPX network numbers that you wish NetSupport Manager to browse. If multiple network numbers are required, separate each with a comma (,).

Connecting to Clients/Controls via a NetSupport Gateway

The primary role of a NetSupport Gateway is to facilitate seamless remote control between PCs that may both be located behind different Firewalls. The Gateway provides a stable and secure method for locating and connecting Clients/Controls via HTTP delivering web based remote control without the need for modifications to existing Firewall configurations.

Typically, companies protect their internal network by using a Firewall, only allowing connections if specific TCP/IP ports have been opened. On occasions you may find that a direct connection between a NetSupport Control and Client is blocked because the Firewall's they are protected by are configured to prevent outgoing connections on all but the standard TCP/IP ports.

A NetSupport Gateway solves this problem by acting as a third party that sits between the Control and Client, the HTTP protocol, rather than TCP/IP, being used for communications.

Notes:

- Client and Control configurations can have both TCP/IP and HTTP enabled simultaneously thus ensuring that local connections are still valid.
 - In version 9.10, Port 443 was introduced as the default for HTTP communications, 3085 being used previously. Gateway settings will be preserved for existing customers who subsequently upgrade, enabling 3085 to continue to be used, but there may be scenarios when upgraded Controls and Clients will need the HTTP Port manually reconfiguring to ensure compatibility.
-


Gateway Installation and Configuration

The Gateway is designed to run on a machine that is accessible from both the Client and Control. It must therefore have a fixed or static IP address.

The Gateway can be installed as a standalone component on the machine you wish to use, or along with other NetSupport components.

Note: You can also configure NetSupport to communicate via Proxy Servers if used.

To install the Gateway component you must select Custom when choosing the type of NetSupport Installation to perform.



You will also need to configure the properties for the Gateway, primarily the Port to use in communications and the encrypted Key for verifying connections from a Control or Client.

Gateway Configuration Utility

You use this dialog to configure the properties of the Gateway. You can access the dialog at the end of the installation, when the dialog will appear automatically, or via the NetSupport Gateway icon which appears in the workstations system tray. Right-click on the icon and select **Configure Gateway**. Alternatively, you can run the file `Pcigwcfg.exe` from the NetSupport Manager program folder.

General Tab

The screenshot shows the 'NetSupport Gateway Configuration Utility' dialog box with the 'General' tab selected. The dialog has four tabs: 'General', 'Keys', 'Users', and 'Redundancy'. The 'General' tab contains three main sections: 'Listening Port and Interfaces', 'Comms. Management Packet Interval', and 'Event Log Files'. In the 'Listening Port and Interfaces' section, the 'Listen on all IP interfaces' radio button is selected, and the 'Port' is set to 443. Below this is a table for 'Listen on specified IP interfaces' with columns for 'IP Address' and 'Port', and buttons for 'Add...', 'Delete', and 'Edit...'. The 'Comms. Management Packet Interval' section has a 'CMPI (secs):' field set to 60. The 'Event Log Files' section has a 'Location:' field set to 'C:\Program Files\NetSupport Manager' and a 'Max. file size (KB):' field set to 1000, with a 'Browse...' button. At the bottom are 'OK', 'Cancel', 'Apply', and 'Help' buttons.

Listening Port and Interfaces

Listen on all IP interfaces

The NetSupport Gateway uses HTTP Port 443 by default.

Note: If the Control and/or Client are located behind a firewall, you will need to enable Port 443 within your firewalls configuration.

Listen on specified IP interfaces

You can add multiple IP addresses or enter a specific IP address, select **Add** and enter the IP address.

Comms. Management Packet Interval

CMPI (secs):

When configured for Gateway connections, the Client workstation confirms its availability by periodically polling the Gateway. By default, a network packet is sent every 60 seconds but you can change this if required.

Event Log Files

Gateway activity during an active session is recorded in a text file, default GW001.LOG. This can be useful for checking which Clients and Controls have connected through the Gateway.

Location:


By default, the log file is stored in the NetSupport Manager program folder. ie c:\program files\netsupport manager\GW001.log. Select Browse to specify an alternative path.

Max File Size (KB):

Over a period of time the log file could become quite large, you can manage this by specifying a maximum file size. When the limit is reached the existing information in the file is overwritten by the new records.

Note: For changes to the log file settings to take affect you will need to restart the Gateway32 service.

Keys Tab




Gateway Keys

This acts as a form of Security Key. The Gateway will not accept connections from a Control or Client unless a “Gateway key” is specified, and that same key is also present at both the Control and Client end. The Gateway can support multiple keys, at least one key must be specified.

Gateway key data is sent encrypted between Client/Control and the Gateway. Once connected to the Gateway all Client/Control security such as user names and security keys will function normally.

Select **Add** to specify the key. The Key must be at least 8 characters.

Users Tab




Restrict remote control access to the following users:

To enhance the security you can restrict remote control access to specified users. At the Control a user will be required to configure a username/password in order to browse a Gateway and connect to Clients.

Once enabled select Add and enter the user details and set a password.

Redundancy Tab



Operate as secondary gateway

You can set up a secondary Gateway to take over when the primary Gateway is not available. The secondary Gateway will act as a backup and once the primary Gateway is available the Clients will switch back to this, but it will not disrupt any active remote control sessions.

Select this option if you wish to use this Gateway as a secondary Gateway.


Primary Gateway:

Enter the IP address of your primary Gateway.

Port:

The NetSupport Gateway uses HTTP Port 443 by default.


Once installed, the NetSupport Gateway icon will appear in the system tray of the workstation. Double-clicking the icon will display a status window listing any current activity through the Gateway.



Note: You will need to note the IP address of the Gateway machine as this will be required when configuring the Control and Client machines. In addition, you will also need the address of your Proxy Server if this is to be used for routing communications.

Client Configuration

The Client machine needs to be configured to use the HTTP protocol and be given the appropriate Gateway access details.



1. From the Basic or Advanced Client Configurator select {Connectivity-HTTP}.
2. Check the Use HTTP box, Port 443 will be configured by default.

3. Confirm which Gateway to use by entering the IP address of the Gateway machine, you can specify a secondary Gateway, which will take over if the primary Gateway is unavailable.
4. Enter the appropriate Gateway Key as set at the Gateway machine.
5. NetSupport can be configured to route communications through a Proxy Server if required. Enter the server address and an appropriate Port, 8080 recommended.
6. You can override the Comms. Management Packet Interval that is set at the Gateway by entering a time here.
7. Click OK.

Control Configuration


As with the Client, HTTP also needs to be enabled at the Control.

1. From the Control Window drop down menu select {Network}{Configure}{Connectivity-HTTP}.
or
To apply the setting to a specific profile, choose {Tools}{Configurations} from the Control Window drop down menu. Select the required profile and choose Connectivity and Startup Settings.
2. Check the Use HTTP box, Port 443 is configured by default.
3. Click OK.

Add Gateways

The Control can communicate with multiple Gateways and the details of each need to be added at the Control end.

1. From the Control Window Tree View select the Gateway folder.
or
Select New from the Control Window toolbar.
2. Choose Add Gateway. The Add a Gateway wizard will appear.



3. Enter a Name and Description for the Gateway. Click Next.
4. Enter the IP Address of the machine where the Gateway is installed and confirm the Port number to use, 443 will be specified by default. If required enter a secondary Gateway to be used if the primary Gateway is unavailable. Click Next.
5. If this Gateway is to communicate through a Proxy Server enter the IP Address and Port to use. Click Next.
6. Enter the Gateway Key. This must match the Key set at the Gateway and Client end.

7. To restrict the use of browsing and controlling remote Clients, enter a username and password. Click Finish.
8. The new Gateway will be added to the list view.
9. Repeat the above process for any other Gateways that the Control needs to use.

Control-Gateway-Client Communications

Now that all the elements are in place, you are ready to attempt connections through the Gateway. The Gateway serves 3 basic purposes:

To receive and store Client registrations

For a Client to be available to a Control it must connect and stay connected to the Gateway. The Client indicates its readiness by periodically polling the Gateway that it has been configured to use. The Gateway stores the Client details in an internal table.

Respond to Browse commands from the Control

Once the Control has added the required Gateways it can Browse them for Clients. The Gateway responds by scanning through its list of available Clients and returning those that match the Browse criteria.

Note: Unlike a standard network Browse, where Known Client details are stored for future use, Gateway Client details are lost when the Control closes. This is because the details are maintained at the Gateway end. Although the Client is permanently connected to the Gateway, the Control is not and therefore needs to Browse the Gateway each time it wants to find Clients.

1. From the Internet Gateways folder in the Control Window Tree View select the required Gateway and double-click Browse Gateway. The Browse Gateway dialog will appear. Enter a partial Client name or leave blank to search for all available Clients.
or
Right-click on the Gateway name in the Tree View and select Open. This will automatically Browse for all available Clients.
2. Found Clients will appear in the List View and you can now connect and remote control them in the usual way.

Note: You can ask for a combined Network and Gateway Browse by selecting Browse from the Control Window Toolbar and checking the **Include Gateway Clients** box. All found Clients will appear in the Browse folder in the Tree View, the Gateway Clients will not be added to the Internet Gateway folder.

Pass all data between connected Controls and Clients

Although data is transferred between the connected Control and Client via the Gateway this will appear seamless and performance will not be affected.

Connecting through Firewalls and Proxy Servers

It is possible to have NetSupport Clients/Controls running on the inside of a Firewall/Proxy Server and still be available for connection to workstations on the outside, without compromising the security of the network. Likewise, you are able to connect to Control and Client workstations running outside Firewalls/Proxy Servers.

Note: While this section provides general guidance, NetSupport's Gateway feature is specifically designed to provide seamless Remote Control between PCs that may both be located behind different Firewalls. The Gateway provides a stable and secure method for connecting Clients and Controls and delivers web based remote control without the need for modifications to existing Firewall configurations. The HTTP protocol on port 443 is used for Gateway communications. You will need to ensure that this port is open within your firewall configuration.

Connecting to Controls and Clients INSIDE Firewalls

For a Control on the external network of a Firewall to connect to Clients on the Firewalls internal network, you must enable some form of address translation. This process translates the address of a workstation on the internal network, which would otherwise be invisible, into an address that is accessible from the external network. You should (depending on the Firewall) be able to specify which IP addresses can access the internal workstation and which Port is open.

TCP/IP Ports Used By NetSupport Control to Client

The NetSupport Control uses TCP/IP port 5405 to send IP requests to Clients, and the NetSupport Client listens on port 5405 for incoming requests from the Control.

Client to Control

With the introduction of the Client Connect feature in NetSupport Manager 5.00, it was necessary for an additional port to be created to ensure that the two methods of connection (Control calling Client, Client calling Control) could run alongside each other without conflict. Port 5421 is registered for this purpose.

Connecting to Controls and Clients INSIDE Proxy Servers

This will not be possible with Proxy Servers, as they will not provide a means of address translation. A Proxy Server, by design, will not allow connections into a protected network.

Connecting from within a Firewall or Proxy Server to a Client on the outside requires the following:

- Port 5405 enabled for outgoing connections on your Firewall or proxy server.
- A Client on the other side listening on the same port number and visible to the Control on the inside of the Firewall/Proxy Server.

Client calling a Control

1. Enable port 5421 for outgoing connections on your Firewall or proxy server.
2. Choose {Call Control} from the NetSupport Client Main Window drop down menu.
3. Enter either the hostname or IP address of the Control you wish to connect to.
4. The Control will then receive a message stating that a Client is attempting to make a connection. They can choose to accept or disconnect the attempt.

Note: Port 5421 is not configurable.

Control calling a Client

1. Choose {Client}{Quick Connect} from the Control Window drop down menu.
2. Enter either the hostname or IP address of the Client you wish to connect to.
3. Click OK.

Note: NetSupport will not communicate directly with a Proxy Server via SOCKS, and will only work if a TCP/IP direct connection is available.


Connecting to a MAC Based System

Using the NetSupport Control you can connect to and remote control a system that has a previously installed VNC Client. NetSupport Manager does not install anything onto these systems itself and only requires the existing VNC Client to be in place.

Note: NetSupport's standard Browse facility will not find the VNC Client, you must use the Add New Client option.

To Connect to a MAC System

1. Select {Client}{New} from the Control Window drop down menu. The **Add a new Client** wizard will appear.



2. Enter a Name for the Client. In the Location field, use the default option, Local. In the Client Type field choose VNC Client from the drop down list. Click Next.
3. Enter the address details of the machine you wish to connect to. NetSupport's default port for VNC connections is 5900. Click Next.
4. Choose the appropriate Video Encoding. Click Next.
5. If required, enter any additional Client properties.
6. Click Finish. The new Client icon will be added to the Control Window List View.

You can now connect to and view the Client.

For information on currently supported features please visit, www.netsupportmanager.com/mac.asp

Implementing NetSupport in a Terminal Server Environment

A NetSupport Control can connect to Clients within a Terminal Server environment.

For ease of implementation NetSupport provides a downloadable setup package which will guide you through the required installation and configuration processes. Our online Knowledge Base provides full instructions, please visit www.netsupportsoftware.com/support and refer to the Technical Document **Setting Up NetSupport to run in a Microsoft Terminal Server Environment (TD127)**.

When the setup is ready you can configure the NetSupport Control to browse for the required Terminal Server Clients.

1. Select {Network}{Configure} from the Control Window drop down menu.
or
To edit a Named Configuration file, choose {Tools}{Configurations} from the Control Window drop down menu. Select the required file and click Connectivity and Startup Settings.
2. From the Configuration options choose Connectivity – TCP/IP.
3. Click Settings. The Configure TCP/IP Client Browsing dialog will appear. Details of any existing Broadcast Addresses will be displayed and you can add your Terminal Server requirements to the list. Click Add.
4. You will be prompted for an IP Browse Address but to enter your Terminal Server address range, click Advanced.
5. In the Advanced Browse dialog enter the IP Address of your Terminal Server and the range of Port Numbers allocated to the Terminal Server Clients. Click OK, the specified browse details will be added to the list of addresses. Click OK to accept the listed Broadcast Addresses.

Enter IP Browse Address (Advanced)

☐ Subnet

Target IP address:

Subnet mask:

☐ Address Range

Base IP address:

No. of clients:

☒ Terminal Services

IP address:

Port range: to

6. Click OK to accept the new TCP/IP settings. To apply the changes immediately click Yes.
7. You can now Browse for your Terminal Server Clients.

Disconnecting a Client

When you have finished remote controlling connected Clients you must disconnect from them before closing your NetSupport session.

To disconnect a Client

1. Choose the Active folder from the Control Window.
2. Select the Client you want to disconnect in the List View.
3. Choose {Client}{Disconnect} from the Control Window drop down menu.

Or,

Right click on the Client icon and choose Disconnect.

Disconnecting all Clients

Rather than disconnecting Clients individually, you can disconnect all connected Clients in a single action.

To disconnect all Clients

1. Choose {Client}{Disconnect All} from the Control Window drop down menu.

Client Automatic Login

If a generic naming convention is used for your PCs, you can automatically log the Clients in to save time.

Note: Client Automatic Login does not support Windows 9X Clients.

To automatically login Client machines

1. Select the Client machine(s) you wish to login.
2. Choose {Client}{Login} from the Control Window drop down menu.
or
Click the Login icon on the Control toolbar.
or
Right Click and choose Login.
3. The Auto Login dialog will appear.

4. Enter the Username, Password and Domain and click Login. The Username will appear once the login has been successful.
5. You can also view Client screens from this dialog, select the required Client and click View.
6. When you have finished click Done to exit.

Client Automatic Update

A quick and easy way to update Clients to the same version as the Control is to use the automatic update facility. Any NetSupport Manager components that are installed on the Client machine will be updated to the current Control version, this is available on version 7.00 and above Clients.

Note: Only available on Windows based Clients.

To Automatically Update the Client

1. Select the Client(s) that you wish to update.
2. Choose {Client}{Update} from the Control Window drop down menu.
Or
Right Click and choose update.
3. The Clients will be updated to the same version as the Control.

Notes:

- The Clients must either be logged in with administrator rights or logged off, for the updates to take place.
 - The Remote Deployment Utilities must be installed on the Control machine to use this function.
 - If disable file transfer and disable execute are selected in the Client Configurator, you will not be able to update the Client.
-

Power Management – Power on/Power off

Power consumption equates largely with heat generation, which is a primary enemy in achieving increased performance. Newer processors are larger and faster, and keeping them cool can be a major concern. With millions of workstations in use, and sometimes hundreds located in the same company, the desire to conserve energy has grown from a non-issue to a real issue in the last five years.

Power Management is a technique that enables hardware and software to minimise system power consumption. It works by shutting down portions of the hardware during periods of low or no use, meaning that the workstation is ready to work when you are and conserve energy when you are not.

See below for special considerations on Windows NT 4.0.

Client Power On

To Power on a NetSupport Client the workstation must have a Wake-on-LAN network adapter and a BIOS that will support it (consult your network adapter documentation for more information), the Client must also be Known to the Control. The Control sends a Wake-on-LAN packet to the Client network adapter which instructs the workstation to Power On.

To Power On a NetSupport Client

1. Select the icon(s) of the Clients you wish to Power On.
2. Choose {Client}{Power On} from the Control Window drop down menu.
Or,
Right click and choose Power On.
Or,
Click the Manage icon on the Control toolbar and choose Power On.
3. The Client workstations will now Power On.

To Power On a Group Of Clients

1. Open the All Computers Folder in the Tree View and select the required Group.
2. Choose {Group}{Power On} from the Control Window drop down menu.
Or,
Right click on the Group and choose Power On.
Or,
Click the Manage icon on the Control toolbar and choose Power On.
3. The Client workstations will now Power On.

Client Power Off

NetSupport uses the Advanced Power Management (APM) features of the Windows operating system (where supported), to provide Client power down capabilities. APM relies on the Client workstation having an ATX motherboard and ATX power supply.

A Control can remotely Power Off a Client workstation using the NetSupport Power Management function.

To Power Off a NetSupport Client

1. Ensure all open applications at the Client workstations are closed.
2. Select the icon(s) of the Clients you wish to Power Off.
3. Choose {Client}{Power Off} from the Control Window drop down menu.
Or,
Right click and choose Power Off.
Or,
Click the Manage icon on the Control toolbar and choose Power Off.
4. The Client workstations will now Power Off.

To Power Off a Group Of Clients

1. Ensure all open applications at the Client workstations are closed.
2. Open the All Computers Folder in the Tree View and select the required Group.
3. Choose {Group}{Power Off} from the Control Window drop down menu.
Or,
Right click on the Group and choose Power Off.
Or,
Click the Manage icon on the Control toolbar and choose Power Off.
4. The Client workstations will now Power Off.

Special Considerations on Windows NT 4.0.

The Windows NT 4.0 operating system does not by default provide APM support and it will be necessary to update the Windows NT 4.0 Hardware Abstraction layer (HAL.DLL) to provide this functionality. Microsoft provide an updated HAL which adds APM support for many systems, for details of how to obtain this please refer to the support area of the NetSupport web site or contact your computer manufacturer to establish if APM can be provided for your system on Windows NT 4.0.

Rebooting or Logging out Clients

Enables a Control to remotely reboot or logoff Client workstations either individually or by selected group.

To reboot or logout a Client

1. Select the Client in the Control Window List View.
2. Choose {Client}{Reboot or Logout} from the Control Window drop down menu.
or
Right-click on the Client icon and select Reboot or Logout.
or
Click the Manage icon on the Control toolbar and choose Reboot or Logout.
3. Click Yes, to confirm send Reboot/Logout.
4. You will be immediately disconnected from the Client.

Or,

1. While Viewing the Client, choose {Client}{Reboot or Logout} from the View Window drop down menu.
or
Select the Reboot or Logout icons from the View Window Toolbar.
2. Click Yes, to confirm send Reboot/Logout.
3. You will be immediately disconnected from the Client.

To reboot or logout a Group of Clients

1. Select the members of the Group in the Control Window List View or the entire Group in the Control Window Tree View.
2. Choose {Group}{Reboot or Logout} from the Control Window drop down menu.
or
Right-click on the group name in the Tree View and select Reboot or Logout.
or
Click the Manage icon on the Control toolbar and choose Reboot or Logout.
3. Click Yes, to confirm send Reboot/Logout to the Group.
4. You will be immediately disconnected from the members of the Group.

Note: Make sure that all workstations within the Group are available and not being used by other staff before you use this function!

Sending Ctrl+Alt+Delete

You can send Ctrl+Alt+Delete to a workstation that you are Viewing or simply connected to.

To send Ctrl+Alt+Delete to a connected Client

1. Press the Ctrl+Alt+Esc keys simultaneously.

Or,

1. Choose {Client}{Send Ctrl+Alt+Delete} from the Control Window drop down menu.

or

Click the Manage icon on the Control toolbar and choose Send Ctrl-Alt-Delete.

or

Right Click and choose Send Ctrl+Alt+Delete

2. Click Yes, to confirm Send Ctrl+Alt+Delete.

To send Ctrl+Alt+Delete to a Client you are Viewing

1. Press the Ctrl+Alt+Esc keys simultaneously.

Or,


1. Choose {Client}{Send Ctrl+Alt+Delete} from the View Window drop down menu.

2. Click Yes, to confirm Send Ctrl+Alt+Delete.

Viewing

The View Window

The View Window is the primary interface for interacting with individual Clients. Each Client has its own View Window. The Client View Windows are used for displaying the screens of the Clients at the Control. You can have multiple Client View Windows open and displayed simultaneously.



The View Window is divided into the following sections:

The Title Bar

This displays the name of the Client that is displayed in the Client Screen Area.


The Menu Bar

The Menu Bar contains a series of drop down menus that can be used to access the various tools and configuration utilities.

The Toolbar

The Toolbar contains shortcuts to many of the most frequently used tasks and tools. Double clicking on an individual item takes you straight to that task or function, eliminating the need to work through the drop down menus. Positioning the cursor over an icon will display a brief description of its function.

Items can be added or removed by right-clicking on the toolbar and selecting customise.



The Client Screen Area

This is used for displaying the screen of the Client.

Viewing Clients

Having connected to a Client, you can now remotely control it. This is called Viewing. The Client's Screen will be displayed in a Window on the Control workstation. NetSupport will allow you to View multiple Client screens, each in its own Window, simultaneously.

To View a Client

1. In the list view, double-click on the required Client's icon.
or,
Right click on the Client's icon and choose {View}.
or,
Click the appropriate Client button in the Quick View Toolbar.
or,
Click the Desktop icon on the Control toolbar and choose View Client.
2. The View Window for that Client will now appear with its screen displayed.

To return to the Control Window

1. Choose {Client}{Close} from the View Window drop down menu.

Viewing Modes

You can View a Client in three modes:

Share

The Client's screen will be displayed at both the Control and the Client. Both the Control and the user at the Client will be able to enter keystrokes and mouse movements.

Watch

The Client's screen will be displayed at both the Control and the Client. Only the user at the Client will be able to enter keystrokes and mouse movements. The user at the Control will be locked out.

Control

The Client's screen will be displayed at both the Control and the Client. Only the user at the Control will be able to enter keystrokes and mouse movements. The user at the Client will be locked out.

To change the View mode

1. Select the mode Share, Watch or Control from the View Toolbar.
Or,
Press PAUSE+ALT keys and select Watch, Share or Control from the View Window {Client} drop down menu.

Maximising the View Area

Viewing a Client in Full Screen Mode, maximises the View Window. What you see is exactly what would be seen on the workstation you are Viewing.

To maximise the View area

1. Choose {View}{Full Screen} from the Client View Window drop down menu.
Or,
Click on the Full Screen icon in the Clients View Window toolbar.
2. The Full Screen dialog will appear.

By default NetSupport will provide you with a floating toolbar while in Full Screen Mode.

Viewing multiple Client screens simultaneously

NetSupport enables you to View multiple Clients screens simultaneously, each in its own Window. You can even scale their individual View Windows to fit on the Control's screen.

To View multiple Client screens

1. View each Client you want to include.
2. From the Control Window drop down menu or any Client {View} drop down menu, choose {Window}{Tile} and then select which NetSupport Windows you want to display.

Your chosen Windows will be tiled on the Control's screen. If you want to see the entire Client's screen then choose the Scale to Fit option in the toolbar of each Client's View Window.

Note: Scale to Fit is set by default. To View the screen in normal resolution, turn off Scale to Fit.

Blanking the Clients screen while Viewing

For security reasons, you may require the Client screen to be blank while you are remotely controlling it.

1. Choose {Client}{Blank screen} from the View Window drop down menu.
2. The Clients screen will be blanked.
3. To restore the screen, choose {Client}{Blank screen} from the View Window drop down menu.

Scale to Fit Mode

Scale to Fit allows you to view a remote screen within the available size of the Remote Window rather than providing you with a series of scroll bars so that you can pan around the screen.

This allows you View multiple screens simultaneously to maintain an overview of a number of selected workstations.

Note: Using Scale to Fit does impact on the quality and clarity of the View, and is designed to allow you to monitor a screen as opposed to work on it. Try it for yourself and decide what level of scaling is acceptable for your purposes.

To view a View Window to scale

1. From the Client View Window, choose {View}{Scale to Fit}.
- Or,
Click on the Scale to Fit icon on the View Toolbar.


Displaying the View Settings for a Client

During any control session where you may be working with more than one Client, you can tailor how each Client interacts with the Control. For example, on one Client you may want to use compression because it is on a slow link, but on another you may want to turn compression off. NetSupport allows you do this by modifying the default settings for the current Control Profile.

To adjust View Settings while viewing

1. Select the Client to view.
2. Choose {View}{Settings for Client} from the View Window drop down menus.
Or,
Select the Settings button on the View Window Toolbar.
3. The Settings dialog will appear.
4. Configure which options will be enabled, when you start a View Session. (Refer to the Control Configuration - Remote Control Settings section of this manual for detailed information about the available options)

Note: If you edit the Client Settings, the changes you make only apply to that Client during the current Control session. If you want to change the settings permanently check the Update Configuration box.




Scanning

The Scan function enables you to cycle through each connected Client in turn, displaying its screen on the Control. It is an alternative to Viewing multiple Clients in scaled windows, which may cause their screens to be unreadable.

Multiple Client screens can also be scanned in one Scan Window.

Scan one Client screen at a time

1. Choose {Tools}{Scan} from the Control Window drop down menu.
or
Click the Desktop icon on the Control toolbar and choose Scan.
2. The Scan dialog will appear.



3. Specify which Clients to Scan by removing or including the check mark next to the Client name.
4. Select the Scan interval.
5. Select Display one Client at a time.
6. Click Scan.
7. The Scan Window will appear and immediately show you the first Client in the sequence. It will cycle through the selected Clients, showing their screens on the Control, until you end the Scan.

Note: If you want to start scanning from a particular Client, select their name in the Scan dialog.

To end a Scan

1. Choose {Scan}{Close} from the Scan Window drop down menu.

Scanning Multiple Client Screens

Multiple Client screens can be scanned simultaneously in one Scan Window.

To Scan multiple screens simultaneously

1. Choose {Tools}{Scan} from the Control Window drop down menu.
or
Click the Desktop icon on the Control toolbar and choose Scan.
2. The Scan dialog will appear.
3. Specify which Clients to Scan by removing or including the check mark next to the Client name.
4. Select Display multiple Clients at a time.
5. Select number of Client screens to be displayed in the Scan Window.
6. If scanning more than four Client screens, select a Scan interval.
7. Click Scan.
8. The Scan Window will appear.


To End the Scan

1. Choose {Scan}{Close} from the Scan Window drop down menu.

The Scan Window

The Scan Window is a special type of View Window that cycles through the selected Client screens, displaying each in turn, for the pre-determined Scan Interval.

The Scan Window, for a single Client scan, is divided into the following sections:



Menu Bar

The Menu Bar contains a series of drop down menus that can be used to access the various tools and configuration utilities.

The Toolbar

The toolbar buttons for a single Client Scan have the following functions: -

Previous, Auto and Next buttons

You can turn auto timing on or off from the Scan Window toolbar, or choose to move forwards or backwards between individual Clients. The previous button shows the previous Client screen scanned. The next button shows the next Clients screen in the scan cycle.

Scaling to Fit

It may be that the Client is running in a higher resolution than the Control. In this case choosing the Scale to Fit option from the View Window Menu or Toolbar, will re-size its screen to fit the Window in which it is displayed.

Full Screen

When Scanning in full screen mode, you can use the Scan Floating toolbar to control the operation.


Capture

A snapshot of the current Client view window will be taken. You will then have the option to name and save the current screen contents to a file.

The Status Bar

The Status Bar indicates which Client you are currently scanning and how far through the Scan interval you are.

The Scan Window, for a multiple Client scan, is divided into the following sections:



Menu Bar

The Menu Bar contains a series of drop down menus that can be used to access the various tools and configuration utilities.

The Toolbar

The toolbar buttons for a multiple Client Scan have the following functions: -

Previous, Auto and Next buttons

You can turn auto timing on or off from the Scan Window toolbar, or choose to move forwards or backwards between individual Clients. The previous button shows the previous Client screen scanned. The next button shows the next Clients screen in the scan cycle.

Scaling to Fit

It may be that the Client is running in a higher resolution than the Control. In this case choosing the Scale to Fit button, will re-size its screen to fit the Window in which it is displayed.

Maximise

To enlarge a Client View Window. This button will be greyed out until you select a Client View Window. To maximise the Client View Window, click the Maximise button or click the box in the top right hand corner of the Client View Window.

Lock

To lock a selected Clients keyboard and mouse.

Chat

To initiate a chat session between a Client and the Control.

Share

To View a Client in Share Mode.

Capture

A snapshot of the current Client view window will be taken. You will then have the option to name and save the current screen contents to a file.

The Status Bar

The Status Bar indicates which Client you are currently scanning and how far through the Scan interval you are.


Thumbnail View / Monitor Mode

Thumbnail View or Monitor Mode, similar to the Scan feature, enables the Control to view multiple Client screens simultaneously.

A convenient thumbnail view of each connected Client screen is displayed at the Control providing a quick and easy method for monitoring Client activity. While in Monitor mode the Control still has access to the full range of NetSupport features such as View, Chat and File Transfer.

If the displayed thumbnail is larger than 128 a selection of icons will be displayed, showing a range of remote control features. Clicking the icon will activate that function for the Client, the icon will be highlighted if any of the features are currently in use for a Client.

1. Display the required Client List by selecting the appropriate folder in the Control Window Tree View. You would generally want to limit the number of displayed Thumbnails to **Connected** Clients only.
2. Choose {View}{Thumbnail} from the Control Window drop down menu.
or
Right-click on a clear area of the List View and select Thumbnail.
or
Click the Monitor icon at the top of the List View.
or
Click the Monitor icon in the Thumbnail Toolbar.



The List View will display each Client thumbnail. By mousing over a thumbnail you can zoom into that screen. Double-clicking a thumbnail will open a view session to that Client, right-click and you can select from the full range of available Client features. For example, by selecting multiple thumbnails you can invite those Clients into a Chat session.

Thumbnails can be re-sized to suit using the slide control at the top of the List View. If the displayed thumbnail width is larger than 128 the current logged on user and Operating System will be displayed on each thumbnail, this data is also available when zooming in on a screen. The frequency at which the displayed data is refreshed can be adjusted in the Control Configuration or by clicking the Update Frequency icon at the top of the List View.

1. Choose {Tools}{Configurations} from the Control Window drop down menu and select the configuration to update.
or
To adjust the currently loaded configuration, choose {View}{Settings for current configuration} or click Settings on the toolbar.
2. Select Control Interface – Settings.
3. Amend the Thumbnail properties as required.

Note: You can also amend the Thumbnail properties by selecting the relevant icon in the Thumbnail Toolbar.

Organising Clients in the List View

Clients can be conveniently organised into categories using a range of criteria including the operating system, connection type etc.

Organising Clients into Categories

1. Choose {View}{Categories} from the Control Window drop down menu.
2. Select the category you wish to organise your Clients by.
3. The Clients will now be grouped by the category in the List view.

Note: Category view is only supported on Windows XP and above.


Launching Applications

This feature allows you to launch (execute) an application on an individual Client workstation or a Group of Client workstation's without the need to remote control them.

Note: The application itself must be installed on or available to the Client workstations.

To Execute an application on a Client Workstation:

1. Open the Active or Browse Folder in the Tree View, select the required Clients.
2. Choose {Client}{Execute at Client} from the Control Window drop down menu.
Or,
Right click on the desired Client(s) in the List View and choose Execute at Client.
Or,
Click the Actions icon on the Control toolbar and choose Execute.
3. The Execute Application dialog will appear.



4. Enter the name and path of the application to execute at the Client.
Or,
Click on Local Browse button and select an executable application on the Control workstation.

Note: Check that Client applications are stored in the same location as the Control to ensure successful execution.

5. Check the box Add to List, to save it for future use in the Saved List Tab.
 6. Confirm the description and path.
 7. Click Execute.
-

Note: If you only want to execute applications to Clients that are logged on select the option "Execute Only if the Client is Logged on".

The application will now be launched at all selected Clients and the result of the operation displayed in the Results Box.

To Execute an application on a Group of Clients

1. Open the All Computers Folder in the Tree View.
2. Right-click on the required Group and choose Execute at Client.
Or,
Choose {Group}{Execute at Client} from the Control Window drop down menu.
Or,
Click the Actions icon on the Control toolbar and choose Execute.
3. The Execute Application dialog will appear.
4. Enter the full path of the application you want to run.
Or,
Click Local Browse and select an executable application on the Control workstation.

Note: Check that Client applications are stored in the same location as the Control to ensure successful execution.

5. Check the box Add to List, to save it for future use in the Saved List Tab.
6. Confirm the description and path.
7. Click Execute.

The application will now be launched at all selected Clients in the Group and the result of the operation displayed in the Results Box.

To Save the details of your executed application for future use

1. Open the Execute dialog box.
2. Select the Execute Tab.
3. Enter the name and path of the executable application.
4. Click Add to List button.
5. The Add/Edit Program details dialog will appear.
6. Confirm the description and path of the executable application.
7. Click OK.
8. Select the Saved List Tab.
9. Check the Show Toolbar box to execute from the Control Window toolbar.
10. Click Close.

A short cut button for easy launching of an application will appear on the Quick Execute toolbar.

To edit a saved Executable application

1. Open the Execute Application dialog.
2. Select the Saved List Tab.
3. Select the Application to edit.
4. Click Edit.
5. The Add/Edit Program details dialog will appear.
6. When finished, click OK.

To remove a saved Executable application


1. Open the Execute Application dialog.
2. Select the Saved List Tab.
3. Select the Application to remove.
4. Click Remove.
5. A confirmation dialog is displayed, click Yes.

User Defined Tools

As well as allowing a Control to launch applications on Client workstations, you can automatically run a task on a Control workstation using a Defined Tool. These tools can also be copied to other Control workstations for use.

To Add a Tool

1. Choose {Tools}{User Defined – Edit} from the Control Window drop down menu.
or
Click Tools-Edit on the toolbar.
2. The User Defined Tools dialog will appear.



3. Click on the Add button.
4. The Add Tool dialog will appear.
5. Choose to add a Program or Script tool by selecting the appropriate Tab.
6. Enter the required information.
7. Click OK.
8. The tool will be listed.

Click Edit to change the properties of a listed Tool or Delete to remove the Tool.

To run a Tool

1. Choose {Tools}{User Defined Tools} from the Control Window drop down menus.
or
Click the Tools icon on the toolbar if available.
2. Select the tool you wish to run.
3. The Tool will automatically run.

To copy User Defined Tool Settings to other Control workstations

1. From the Control Configurator, select File Locations.
2. The Tools file section, click on the Change button.
3. Specify and alternate location or name for the Tools file.
4. Make this file available to Control workstation that is going to adopt this Tools file.
5. From the workstations Control Configurator, {File Locations – Tools file section}, click on the Change button.
6. Select the new Tools file, click Open.
7. The new Tools file will be implemented.

Showing the Control screen to Clients

As well as enabling you to remote control Clients, NetSupport allows you to show your screen to: -


- a selected individual Client.
- a pre-defined group of Clients.
- an ad hoc selection of Clients.
- replay files can also be shown to Clients.

Notes:

- During a show NetSupport displays in real-time all actions undertaken by the Control. In addition, the Control has the option to enable 'Hotkeys' ensuring that any key combinations, e.g. CTRL+V, used by the Control during the show are also visible to the Clients. If using a mixture of key combinations e.g. ALT+V+T, NetSupport will only display two consecutive keystrokes at any one time. The key combinations will not appear if your taskbar is not active.
 - When showing the Control screen to Clients, the screen information is sent to each Client machine in turn. In some network environments where there is limited network bandwidth available or when showing to larger numbers of machines this can affect performance. In these circumstances, NetSupport's Broadcast Show facility can be enabled, see Configuring the Control, Connectivity. This results in the screen information being sent to all machines simultaneously thus improving the speed of transfer. Whilst reducing overall network traffic generated by NetSupport, using this feature will generate additional broadcast packets on your network. It is recommended that you consult your Network administrator before using this feature.
 - The broadcast show feature is only supported in version 7.10 or higher.
-

To Show a Control screen

1. Select the connected Client you wish to Show to.
2. Choose {Tools}{Show} from the Control Window drop down menu.
Or,
Click the Desktop icon on the Control toolbar and choose Show.
3. The Show Configuration dialog will appear.



In this dialog, you must select the Client, or Clients, that you will Show your screen or replay file to. If you are connected to only one Client, or have selected a specific Client before choosing Show, they will appear as an individual option. If you only want to Show to this Client, click Show, otherwise make your selection as follows:

These Clients

The list displays all of the connected Clients and their descriptions. If you are only connected to one Client, this list is disabled. Once you have chosen the Clients you want to Show to, click Show.

Create Replay File at Client

The Show session can be recorded and stored in a Replay File giving Clients the opportunity to playback the session at a later date.

Show Hotkeys

To ensure that all actions performed by the Control are visible to the Clients during a show you can enable the use of Hotkeys. Any key combinations that the Control uses, e.g. CTRL+V, will be displayed in a balloon at both the Control and Tutor screens.

Notes:

- If using a mixture of key combinations e.g. ALT+V+T, NetSupport will only display two consecutive keystrokes at any one time.
 - This utility is only supported on Windows 2000, XP and above.
-

Set Show Mode at Client (Windowed, Full Screen or Maximise Window)

This option allows you to Show at the Client either in a small window, full screen or maximised window. When showing in windowed and maximised window size the Clients Mouse and Keyboard are not locked.

Enable Audio Support

This turns Audio Support on. If you are Showing to only one Client, both the Control and Client can speak. If you are Showing to many, only the Control can speak (Announce). See Using Audio Support for details.

Screen Scrape

NetSupport's favoured, and the most efficient, method for capturing screen data is to hook into the Video Driver of the workstation being viewed. However, there may be occasions when this method will not work because certain applications bypass the driver. In these circumstances you can enable 'screen scrape' mode in order to take a snapshot of the screen. Although this will have a greater impact on the network it will at least provide an accurate representation of the Client's screen.

Send Physical Fonts


In order to reduce the volume of data being sent when sharing information of this nature, NetSupport passes the font information by reference. The target workstation will refer to it's own internal font mappings to find an appropriate match to the one that has been sent. In most cases the same fonts will be available but if there are instances where this isn't the case you can send the full information. Check this box to enable.

Select what you would like to Show

NetSupport will identify if the Control is running multiple monitors, giving you the option to choose which one to Show from the drop down list. If you are unsure which is the correct screen, click Identify. Alternatively, select Whole Desktop to show all.

To End the Show

1. Click on the NetSupport button on the taskbar.
Or,
Right click on the NetSupport icon on the taskbar.
2. This will display the Showing dialog.



The buttons have the following purposes: -

End

Ends the Show and releases the Client's screens and keyboards.

Resume

Resumes the Show.

Continue

The Client's screens and keyboards will remain locked while you prepare other work at the Control. They will not be able to see what you are doing. Effectively the Show is suspended.

Note: In order to Show to a Client from the Control you must first have installed the Client programs on the Control workstation. However, it does not need to be activated.

Showing a Client's screen on a number of Client screens

With NetSupport, it is possible to Show the Control's screen to a number of connected Clients. It is also possible to Show a Clients screen to a number of other connected Clients. This is known as Exhibiting.

For example, it may be that workstation_1 has an application on it that you need to Show to the Accounts department. Therefore, by Viewing workstation_1 and then Showing to all members of the Accounts department, they will now be able to see workstation_1's screen.

To Show a Clients screen

1. Connect to the Clients you wish to Show to and the Client you wish to View.
2. View the Client whose screen you wish to Show.
3. Choose {Tools}{Show} from the Control Window drop down menu.
Or,
Select the Show icon on the Toolbar.
4. Choose Show to 'These Clients'.
5. Exclude the Client you are currently Viewing from the Show: the green tick should be changed to a red cross. If you don't do this, you will get an error saying that the Control cannot Show to this Client while you are Viewing it.
6. Click Show to start the Show.


The Client's screen that is being Viewed will be shown to the other Clients. You can use features such as Scale to Fit and Full Screen to Show more of the Client's screen.

Show Application

The Show feature enables you to display the Control screen to Clients. However, if a number of programs are open at the Control, there may be occasions when you want to show a single application in isolation.

To Show an Application

1. Choose {Tools}{Show Application} from the Control Window drop down menu.
2. The Show Application dialog will appear.



3. Drag the icon to the required application on the Controls desktop and release. (A pink border will appear around the selected application as you move the mouse around the desktop)

or

Click Select and choose the application from the displayed list.

Note: NetSupport will identify if the Control is running multiple monitors, giving you the option to confirm which one the selected application is sited on. If you are unsure which is the correct screen, click Identify. If only one monitor is detected, select Whole Desktop.

4. Choose the Clients to include in the Show.
5. Set additional Show Options if required.
6. Click Show.

Audio Support

NetSupport allows you to use audible communications to Connected Clients, via microphones, headphones and speakers. This can be used while Viewing a Clients screen, Showing your screen to a Client on their workstation or outside of a remote control session by selecting the required Client. NetSupport will only operate Audio if the workstations have Audio Support Installed.

Using Audio Support

1. Right Click the required Client in the List View and select Audio.
2. The Audio toolbar will be displayed.



From here you can: -

- Turn Audio on or off;
- Enable only the Control or the Client to talk;
- Set the microphone sensitivity;
- Select the Audio Quality.

Minimising the Audio toolbar will disable the current audio session, this can be re-started by activating the toolbar. You can start more than one audio session, but only one session can be active at any one time.

To use Audio Support when Viewing

1. Click on the Audio Button on the Toolbar in the View Window.
2. The Audio options will be displayed. These are the same options as on the Audio Toolbar.

The Mute Button turns the speaker and microphone on and off.

To use Audio Support when Showing

1. In the Show dialog box select the check box Enable Audio Support.
2. The Audio Settings set in the Control Configurator Audio option will apply during these sessions.

Audio Announcements

This feature sends an audible announcement to all selected Clients headphones or speakers. They will be able to hear the Control but will not be able to speak back.

Making an Announcement

1. Click on {Tools}{Announce} from the Control Window drop down menu bar.
2. The Announce dialog box will appear, include (green tick), or exclude (red cross), Clients from the announcement, then click Announce.
3. A dialog will appear, indicating that you can now announce. Click OK when you have finished speaking.

Adjusting Microphone and Speaker Volume

You can adjust the audio settings within NetSupport to match the capabilities of your multimedia workstations or to fine tune performance. However, you should note that the higher the quality of sound you select the greater the volume of data that needs to be sent. This can affect screen update performance on slower workstations.

To Access the Volume Controls

1. Right click on the speaker icon in the task bar.

To change other options, such as sound quality, do one of the following: -

Global Method (Changes default setting for all Clients)

1. Choose {View}{Settings for Current Configuration}{Remote Control – Audio} from the Control Window drop down menu.

Individual Client Method (While Viewing):

1. While Viewing the Client.
2. Choose {View}{Settings for Client – Audio} from the View Window drop down menu.
Or,
Click on the Settings button on the View Window Toolbar and select Audio.
Or,
Click on the Audio button on the View Window Toolbar.

In both cases, the Audio Setting dialog will be displayed. This allows you to set the following properties:

Volume Settings adjustments

Threshold	Microphone sensitivity
Microphone	Volume of microphone
Speaker	Volume of speakers
Wave	Volume of Operating Systems Sound Effects

Enable Options

On	Turn Audio on
Off	Turn Audio off
Talk	Set the Control Audio to Talk function only
Listen	Set the Control Audio to Listen function only

Video Player Support

NetSupport provides exceptional multimedia support with full Audio, Video and Remote Control capabilities. This section deals specifically with the use of the NetSupport Video Player.

While the NetSupport Video Player can be used for viewing a video file on an individual workstation, the combination of NetSupport's remote control capabilities with full Audio Support allows you to use this tool to enhance training sessions and demonstrations. By running a Show, then launching NetSupport Video Player, all Clients will be able to watch video files from their own workstations, with full audio support.

The Video Player supports all standard video files for example, avi and mpg. The Video Player runs locally on each Client workstation while the video file can be accessed locally or on a network drive. If video files are stored locally, network traffic is restricted to video player controls and synchronisation and is therefore minimal, making it possible to control video sequences running on a larger number of workstations simultaneously.

If video files are stored on a network drive and Clients have to retrieve files across the network there will be a greater impact on the network. For optimum performance, store the video files locally on each workstation, you may wish to use File Distribution to do this.

Other influencing factors will be:

- The number of Client workstations accessing the file;
- The speed of the network eg: 10/100 MB;
- The size of the video file;
- Client workstation memory/performance specification;
- Other traffic on the network.

Notes

- If a Client workstation is required to retrieve files from a Server, for smooth operation, ensure that the Client workstation has sufficient access rights to the relevant drive and files.
 - The video adapter of the workstation and how the screen resolution is configured will affect the quality of the display.
-

To Play a Video file on a workstation

1. Perform a Show to the Client workstations you want to watch the video file.
2. While performing the Show, launch NetSupport Video Player by double clicking on the NetSupport Video Player icon in the NetSupport Program Folder.
3. The Video Player control panel will appear.
4. Choose {File}{Open} from the Video Player drop down menus to select the correct video file.
5. The Video Player video screen will then appear below the toolbar with the selected file loaded, ready to be played.

Note: NetSupport's Video Player utilises the Audio Support software and hardware installed on your operating system, please adjust these to suit your needs.

6. Click on the Play button on the Video Player toolbar.
Or,
Choose {Play}{Play} from the Video Player drop down menus.

To Pause or Stop a Video file and return to the beginning while it is playing

1. Click on the Pause or Stop button on the toolbar.
Or,
Choose {Play}{Stop or Pause} from the Video Player drop down menus.

Note: The Pause command blanks any Clients video screens you may be Showing the Video file to.

To return to the beginning of the video file


1. Click on the Start button on the toolbar to return to the beginning of the Video file.
Or,
Choose {Play}{Start} from the Video Player drop down menus.

To fast forward to the end of the video file

1. Click on the End button on the toolbar to fast forward to the end of the Video file.
Or,
Choose {Play}{End} from the Video Player drop down menus.

Video Player Control Panel

The Video Player Control Panel operates in a similar manner to standard audio and visual aids. Although the commands on the toolbar perform the same actions as would be expected, please find a detailed explanation below:



File Menu

The File drop down menu contains the following options:

Open

Allows you to select and load the appropriate video file.

Close

Closes the open video file.

Exit

Shuts down the Video Player.

View Menu

The View drop down menu contains the following options:

Text Labels

Hides and displays text labels on the Video Player toolbar.

Toolbar

Hides and displays the Video Player toolbar.

Status Bar

Hides and displays the Status Bar of the Video Player.

Zoom

Resizes the video screen

Play Menu

The Play drop down menu contains the following options:

Play

Starts the loaded video file.

Stop

Returns to the beginning of the loaded video file.

Pause

Blanks the Clients video screen and pauses the video file at the Control workstation.

Start

Returns to the beginning of the video file.

End

Fast-forwards to the end of the video file.

Mute Clients

If Clients are not using headphones while they are watching a video, the sound coming from each workstation can be distracting. This option turns audio off at the Client workstations but leaves it on at the Control machine.

Help Menu

Provides access to the on-line Help and general Version information.

Replay Files

During a Remote Control session the screen, keyboard and mouse activity at a Client or Control PC can be recorded, stored in a file and played back. If the PCs are configured for Audio, any narration that takes place can also be recorded.


A Control can determine how and when recordings take place by enabling the appropriate configuration options:

- Local Recording
- At individual or all Client PCs

Recording Local Activity

Activity at the local machine can be recorded and played back. If required, the Replay File can also be 'shown' to remote Clients.

1. Choose {Tools}{Record} from the Control Window drop down menu.
or
Click the Desktop icon on the Control toolbar and choose Record.
2. The Record Local Activity dialog will appear.



3. **Include Audio**
In addition to the screen, mouse and keyboard activity, if the workstation is configured for Audio, you can record any narration that takes place. Check this box to enable.
4. **Record Physical Fonts**
In order to reduce the volume of data being sent when sharing information of this nature, NetSupport passes the font information by reference. The target workstation will refer to it's own internal font mappings to find an appropriate match to the one that has been sent. In most cases the same fonts will be available but if there are instances where this isn't the case you can send the full information. Check this box to enable.

5. In Directory

- Specify where you want the Replay Files stored. In order to identify each file, filenames will be prefixed with 'Local' and the date and time of the recording.
6. Click OK to start recording. The Recording icon will appear in the task bar.
7. To stop recording, double click the Recording icon.

Recording Replay Files At Client PCs

Activity at remote PCs is recorded when a Control 'Views' a Client that is configured to Record Replay Files. The option can be enabled at individual Client level or set globally.

Record Replay Files For All Viewed Clients

This procedure enables the Control to create a Replay File each time it 'views' a Client PC. The settings can be applied to the current control configuration or to a 'named' configuration.

1. To amend the current configuration choose {View}{Settings for current configuration} from the Control Window drop down menu.
or
Click Settings on the toolbar.
or
To apply the changes to a named configuration, choose {Tools}{Configurations} from the Control Window drop down menu. Select the named configuration and click Settings.
2. The Settings for Configuration dialog will appear.
3. Choose Security - Replay Files and enable the appropriate options. **See** *Configuring The Control - Security Options – Replay Files* for more information.

Record Replay Files for Individual Clients

This procedure enables Replay Files to be created at machines where the Client Configuration has the Record Replay Files option enabled.

1. Run the Advanced Client Configurator at the required PCs.
2. Select the profile to amend.
3. Select Security - Replay Files and enable the appropriate options. **See** *Configuring the Client - Security Options – Replay File Settings* for more information.

Watching Recorded Replay Files

Replay Files can be watched by Controls with appropriate access levels to the files, these in turn, can be shown to Clients.


At a local level, the NetSupport Client program also provides a Replay option enabling Clients to launch files.

At the Control

1. Choose {Tools}{Replay} from the Control Window drop down menu.
or
Click the Desktop icon on the Control toolbar and choose Replay.
2. Navigate to the Directory where the Replay Files are stored.
3. Select the file to replay.
4. Click Open. The Replay Window will appear. Use the Replay Controls to Start/Stop the file.

At the Client


1. Right-click on the NetSupport Client icon in the system tray and choose Replay.
or
Double-click on the Client Icon and choose {Commands}{Replay} from the drop down menu.
2. Navigate to the Directory where the Replay Files are stored.
3. Select the file to replay.
4. Click Open. The Replay Window will appear. Use the Replay Controls to Start/Stop the file.



Showing Replay Files to Clients

Replay Files can be watched by individual Controls and Clients. The Control also has the option of 'showing' a specific file to multiple Clients.

1. Choose {Tools}{Show Replay} from the Control Window drop down menu.
2. The Show Replay dialog will appear.




3. Browse for and select the required Replay File.
4. From the Client list, select the Clients to show the Replay File to.
5. Set additional Show Options if required.
6. Click Show.
7. The Replay Window will open at the Control machine and start playing the Replay File to the selected Clients.
8. Click End on the Replay Window toolbar to end the show.

File Transfer

The File Transfer Window

When you choose to perform a File Transfer operation on an individual Client, the File Transfer Window is displayed. At its simplest, you transfer files by dragging them from one location to another.



The File Transfer Window is divided into five sections

The Title Bar

This shows which Client this particular File Transfer Window is working with.

The Menu Bar

The Menu Bar contains a series of drop down menus that can be used to access the various tools and configuration utilities.

The Toolbar

The Toolbar contains shortcuts to many of the most frequently used tasks and tools. Double clicking on an individual item takes you straight to that task or function, eliminating the need to work through the drop down menus. Positioning the cursor over an icon will display a brief description of its function.

The Local Pane

The Local Pane displays a Tree View of the Directories of the Control on the Left-hand side, and a List View of the contents of those directories on the Right-hand side. Right-click on any item in one of the columns in the list view and a range of context-sensitive functions become available.

The Remote Pane

The Remote Pane displays a Tree View of the Directories of the Client on the Left-hand side and a List View of the contents of those directories on the Right-hand side. Right-click on any item in one of the columns in the list view and a range of context-sensitive functions become available.

Copying Files and Directories

NetSupport includes sophisticated File Transfer functionality that enables you to transfer files to and from a Control and Client workstation.

Notes:

- To help improve performance, NetSupport Manager uses Delta File Transfer technology meaning that only the changed parts of a file that may already exist in the destination directory are transferred. This can prove most useful when updating database files between two locations where either bandwidth usage or availability is an issue.
 - File Transfer functionality can be configured by choosing {View}{Settings for current configuration - File Transfer} from the Control Window drop down menu.
-

To copy files and Directories from a Control to a Client

1. Select the required Client in the List View.
 2. Choose {Client}{File Transfer} from the Control drop down menu.
or,
Click the File icon on the Control toolbar and choose File Transfer.
or,
Right-click on the Client icon in the list view and choose File Transfer.
or,
If you are Viewing the Client, choose File Transfer from the View Window toolbar.
 3. The File Transfer Window to that Client will open.
 4. From the Client Tree View, select the destination drive or directory into which the items will be copied.
 5. From the Control List select the item(s) to be copied to the Client.
 6. Click on the toolbar Copy File button.
 7. A confirmation dialog will be displayed, click Yes.
-

Note: The selected item(s) can also be 'dragged' from the Control List and 'dropped' into the destination drive or directory in the Client View.

To copy files and Directories from a Client to a Control

1. Select the required Client in the List View.
2. Choose {Client}{File Transfer} from the Control drop down menu.
or,
Click the File icon on the Control toolbar and choose FileTransfer.
or,
Right-click on the Client icon in the list view and choose File Transfer.
or,
If you are Viewing the Client, choose File Transfer from the View Window toolbar.
3. The File Transfer Window to that Client will open.
4. From the Control Tree View, select the destination drive or directory into which the items will be copied.
5. From the Client List View, select the item(s) to be copied to the Control.
6. Click on the toolbar Copy File button.
7. A confirmation dialog will be displayed, click Yes.

To transfer files between Clients

With NetSupport's File Transfer it is also possible to copy files and directories between two Clients. To do this, connect to each Client and display the File Transfer Window for each.

Arrange the File Transfer Windows so you can see both and simply drag file/directories from one Client to the other.

You can see more of a Clients files and directories by moving the horizontal sizing bar or clicking on the maximise button located above the Clients directory tree.

Deleting Files and Directories

You can delete files and directories from either a Control or Client machine using the File Transfer Window.

To delete a file

1. Select the file you wish to delete.
2. Click on the toolbar Delete button.
3. A confirmation dialog will be displayed, click Yes

To delete a Directory

1. Select the Directory you wish to delete.
2. Click on the toolbar Delete button.
3. The Remove Directory dialog will be displayed.
4. Select the Include Contents check box.
5. Click Yes.

Note: You cannot remove more than one Directory at a time. If you have several directories selected in the List View when performing the Delete operation, only the last selected Directory will be removed.

Creating Directories

1. Select the Client or Control Tree View.
2. Select the drive or directory in which the directory you want to create will appear.
3. Click on the toolbar Create button.
4. The Create Directory dialog will be displayed.
5. Enter a name for the directory, click OK.

Renaming Files

1. Select either the Control or Client pane List View.
2. Select the file to be renamed.
3. Click on the toolbar **Rename** button.
4. Enter the new name for the file in the black boarder next the file icon.
5. Press the **Enter** key when finished

Changing File Attributes

There may be times when you want to change the attributes of a file, for example to read only.

To change a files attribute

1. Open a File Transfer session to the desired Client.
2. Select the File whose attributes you want to view or change.
3. Right click and choose Properties.
Or,
From the drop down menu bar choose {File} {Properties}.
4. The File Properties dialog will appear.
5. Check or uncheck the attributes you wish to set.

Print File Transfer List

The File Transfer Window provides an option to print a list of files from either the local or remote pane. This can be useful if a record of file transfer operations is required.

You can print a complete directory tree or file list or a selected area.

To Print a Directory or File List

1. Select the required Client in the List View.
2. Choose {Client}{File Transfer} from the Control Window drop down menu.
Or,
Select the File Transfer icon on the Control Toolbar.
Or,
Right click and select File Transfer.
Or,
If you are Viewing the Client, choose {Tools}{File Transfer} from the View Window drop down menu.
3. The File Transfer Window to that Client will open.
4. In either the local or remote pane, select the directory tree or individual file list to be printed.
5. Select {View}{Print} from the File Transfer Window drop down menu. The Print Options dialog will appear.
6. Confirm whether you are printing a directory tree or file list and if it is the full list or selected area. You can also choose to include the application icon appropriate to each file by checking the Print Images box.
7. Click OK to print.

Synchronising Directories

You can synchronise the contents of selected directories on the Control and Client. When you synchronise two directories, any new or updated files in either directory will be automatically copied to the other directory.

To synchronise Directories

1. Select the Control Directory from the Control Tree View to be synchronised with the Client.
2. Select the Client Directory from the Client Tree View to be synchronised with the Control.
3. Click on the toolbar Synchronise button.
4. The Synchronise Directories dialog will be displayed.
5. Check the displayed paths of the two selected Directories.
6. Choose to include the subdirectories by selecting the Include Subdirectories check box.
7. Choose OK.
8. A confirmation dialog will be displayed, click Yes.
9. The Directory Synchronisation Progress dialog will be displayed.
10. When completed, the result will be displayed in the Directory Synchronisation Results dialog box.
11. Read, click OK

Arranging multiple File Transfer Windows

Just as you can View to more than one Client at a time, you can have more than one File Transfer Windows open at a time. These File Transfer Windows can be easily arranged using the commands in the Window, Tile submenu.

To arrange multiple File Transfer Windows

1. Make sure a File Transfer Window or the Control Window is active.
2. Choose {Window}{Tile – File Transfer Windows} from the Control Window drop down menus.
3. All open File Transfer Windows will be arranged so that they proportionality fill the Control workstation screen.

Notes

- When working with multiple File Transfer Windows, refer to the File Transfer Window's title bar to check which Client is being viewed in a particular File Transfer Window.
 - You can use the Tile Windows function, to similarly arrange all open View and Control Windows.
-

Applying a filter to files in List View

You can specify a filter to the contents of a Control or Client's List View, so that only file names which met a certain criteria will be displayed. To do this, use the Filter text boxes located above both panes' List Views.

Any filter settings applied to the Control Panel will not affect the display of the Client pane and vice versa.

Filter settings will remain applied to a Control or Client pane until you reset them or close the File Transfer Window.

To apply a filter to files in the List View

1. Click in the Filter text box above the pane whose List View you wish to filter.
2. Replace the default filter (*.*) with your own, for example, if you wanted to view all file names beginning with the letter MKT, then you would type MKT*.* in the Filter text box.
3. Press the Enter key to apply the filter

To reset the filter to files in the List View

1. Click in the Filter text box above the pane whose List View you wish to reset.
2. Replace the contents of the Filter text box with (*.*), this is the default filter and means no filter will be applied to the files in the current List View.
3. Press the Enter key to apply the filter.

Changing the View format in the File Transfer Window

The contents of the List Views of the Control pane and Client pane can be displayed in different formats. You can also sort the contents of the List Views in order to make them easier to navigate.

There are two types of view in which you can display the contents of the List View in a File Transfer Window:

Name Only view	Displays only the file and directory names
Details view	Displays the file and directory names, along with related details which are displayed in adjacent columns.

To change the Name Only view

1. Click on Name Only button on the far right of the File Transfer Window.

To change the Details View.

1. Click the Detail button on the far right of the File Transfer Window.

Note: You can also change the view type, choose {View}{Show Details} from the File Transfer Window drop down menus.

Changing the sort orders in a File Transfer Window

Typically, the contents of List Views in a File Transfer Window can be sorted into the following orders:

Sort Order	Description
By Name	The contents will be sorted alphanumerically by file name.
By Type	The contents will be sorted alphanumerically by file extension. This is not applicable to drives and directories in the List View.
By Modified Date	The contents will be sorted according to the date they were last modified.
By Size	The contents will be sorted according to the size of the file. This is not applicable to drives and directories in the List View.
By Short Name	The contents will be sorted alphanumerically using the shortened versions of their names.

Note: You can also specify whether the contents are to be sorted in ascending or descending order.

To change the sort order


1. Select the appropriate pane (Control or Client).
2. Click the Sort Order button on the right hand side of the File Transfer Window.
3. A drop down menu will be displayed.
4. Select a Sort Order command.

Note: When the List View is displayed in Details View, you can click on the Column headings, such as Name and Description, to sort the order by an appropriate column heading. Clicking on a column heading the second time will toggle the order direction. The current order direction will be indicated by a small arrow on the right of the column heading, by which the List View is sorted, for example, an arrow pointing up indicates the List is sorted in ascending order.

File Distribution

The File Distribution Window

The File Distribution Window is used for distributing files to multiple Clients, simultaneously.



The File Distribution Window is divided into five sections

The Title Bar

This shows which group of client this particular File Distribution Window is working with.

The Menu Bar

The Menu Bar contains a series of drop down menus that can be used to access the various tools and configuration utilities.

The Toolbar

The Toolbar contains shortcuts to many of the most frequently used tasks and tools. Double clicking on an individual item takes you straight to that task or function, eliminating the need to work through the drop down menus. Positioning the cursor over an icon will display a brief description of its function.

The Local Pane

The Local Pane displays a Tree View of the Directories of the Control on the left-hand side and a List View of the contents of those directories on the left-hand side. Right-click on any item in one of the columns in the list view and a range of context-sensitive functions become available.

The Remote Pane

The Remote Pane shows the Clients to whom the Files will be distributed. Right-click on any item in one of the columns in the list view and a range of context-sensitive functions become available.

Distributing Files

You can Distribute Files to

- All connected Clients;
- Selected Clients;
- A pre-defined Group of Clients.

To Distribute Files to a defined Group of Clients

1. Select the Group of Clients you wish to distribute files to from the All Computers Folder in the Tree View.
2. Choose {Group}{File Distribution} from the Control Window drop down menu.
or
Click the File icon on the Control toolbar and choose File Distribution.
3. The File Distribution Window will appear.
4. From the Local Pane Tree View, select the item(s) to be copied to the Clients.
5. The location on the Client workstations where the files/directories are copied to, is called the Destination Directory. Unless otherwise specified, the Client Destination Directory will be the same as the item(s) location on the Control workstation. If the Client does not have the same Directory available, the item(s) will be copied to the C Drive by default and the folders automatically created.
Or,
To set a specific Destination Directory on the Client workstation, right click on the Client icon in the Remote Pane and choose Set Destination. Specify a destination, click OK.
6. Click Copy.


To Distribute Files to a selected number of Clients

1. Open the All Computers, Browse or Active Folder in the Tree View.
2. Choose {Tools}{File Distribution} from the Control Window drop down menu.
or
Click the File icon on the Control toolbar and choose File Distribution.
3. The File Distribution Window will appear.
4. In the Remote Pane indicate which Clients you wish to copy files to by checking the tick box beside the Client name.
5. From the Local Pane Tree View, select the item(s) to be copied to the Clients.
6. The location on the Client workstations where the files/directories are copied to, is called the Destination Directory. Unless otherwise specified, the Client Destination Directory will be the same as the item(s) location on the Control workstation. If the Client does not have the same Directory available, the item(s) will be copied to the C Drive by default and the folders automatically created.
Or,
To set a specific Destination Directory on the Client workstation, right click on the Client icon in the Remote Pane and choose Set Destination. Specify a destination, click OK.
7. Click Copy.

File Manager

The File Manager Window

The NetSupport File Manager serves the same purpose as Microsoft Explorer. Rather than exiting the NetSupport program and editing the Control workstation, do it from within NetSupport Manager.



The File Manager Window is divided into four sections

The Title Bar

This shows which Client this particular File Transfer Window is working with.

The Menu Bar

The Menu Bar contains a series of drop down menus that can be used to access the various tools and configuration utilities.

The Toolbar

The Toolbar contains shortcuts to many of the most frequently used tasks and tools. Double clicking on an individual item takes you straight to that task or function, eliminating the need to work through the drop down menus. Positioning the cursor over an icon will display a brief description of its function.

The Local Pane

The Local Pane displays a Tree View of the Directories of the Control on the Left-hand side and a List View of the contents of those directories on the left-hand side. Right-click on any item in one of the columns in the list view and a range of context-sensitive functions become available.

Managing Files on the Control workstation

You can manage files on a Control workstation using the File Manager Window. This is similar to the File Transfer Window, but only displays the contents of the Control workstation.

To display the File Manager Window

1. Choose {Tools}{File Manager} from the Control Window drop down menu or click the File icon on the Control toolbar and choose File Manager.

The Tree View

- To select a drive or directory in the Tree View, simply click on it, the contents of the selected item will then be displayed in the List View (on the right).
- If the selected drive or directory contains subdirectories that are not displayed, then a cross symbol will be displayed to the left of the item.
- To expand the contents of a drive or directory so that its subdirectories are visible in the Tree View, either double click on the drive or on the directory, or click on the cross symbol to the left of the drive or directory you wish to expand.

The List View


- To select an item in the List View, simply click on it.
- To select multiple items in the List View:
 1. If the items are adjacent to one another, select the first item, hold down the Shift Key and then select the last item.
 2. If the items are not adjacent to one another, then select the first item, then hold down the Control Key and select each of the other items.
 3. If all files and/or directories are required choose {View}{Select} from the drop down menu or right-click on one of the items in the list view (not the filename) and choose Select. You can highlight all items in the current list or just the files or directories.
- To display the contents of the drive or directory that is one level up from the current directory, double click on the previous directory item at the top of the List View.

Control/Client Chat Sessions

NetSupport allows you to 'Chat' to any number of connected Clients simultaneously, via a scrolling text window. A 'Whiteboard' facility can also be introduced during the Chat session enabling a range of screen annotation tools to be used.

To hold a Chat session

1. Select the Clients or Group of Clients you want to Chat to in the List View. If you do not select a Client icon, all connected Clients will be included.
2. Choose {Client}{Chat} from the Control Window drop down menu.
Or,
Click the Actions icon on the Control toolbar and choose Chat.
Or,
Right click on an individual Client and choose Chat.
3. The Create Discussion Dialog will appear.



The Dialog has the following options:

Topic

If required, enter a title or description for the subject to be discussed in the Chat session. This will appear in the Title Bar of the Chat Window that is displayed at the Client machines. If left blank, the Control Name will appear.

Members

To exclude Clients from the Chat session, remove the check mark next to the Client name.

Options

Members can decline to join

If checked, a message will appear at the Clients machine inviting them to join the Chat session. They can choose to Join or Decline.

Members can't leave the chat


If checked, the option for Clients to Leave the Chat session will be removed.

Chat Window is always visible

If checked, the Chat Window remains on the Clients desktop for the duration of the Chat session. Members cannot minimise the Window.

Confirm which Clients to include in the Chat session and select any additional properties that should apply. Click OK to start the Chat session.

4. The Chat Window will appear on the Control and Client workstations.



The Chat Window

This Window is displayed at each participating members machine and lists the progress of the Chat session.

Unless the option is disabled in the Create Discussion dialog, Clients can choose to Leave the session.

The following options are available from the Chat Window:-

Chat Menu

The content of a Chat session can be stored for future reference. Choose **Save** to create a file containing the text or choose **Copy** to be able to paste the Chat content into another application or file.

Should the Chat members not respond, you can send an audible beep to each workstation by selecting **Send Beep**. (The Client can also do this from their Chat Window) You can configure the Client and Control workstations to play the beep through either the PCs internal speaker, the default, or via the installed sound card to speakers attached to the PC. Select Client Configuration - Client Settings or Control Configuration - Settings.

Window Menu

Only the Control's Chat Window will have a Window drop down menu. This menu enables you to swap between opened screens or Tile them.

Chat Progress

The main body of the Chat Window is used to record the progress of a Chat session. It holds details of members who have joined or left the discussion, as well as the messages that have been sent by each member.

Message

This is where you type your comments. Type the message and hit Enter or click **Send**.

Auto Send

Each message is restricted to 128 characters. Check this box to automatically send the message when the limit is reached.

Close

Ends the Chat session.

Members

Members currently included in the Chat session are listed here. The Control can add or remove Clients from the Chat session as required. Unless disabled, Clients have the option to Leave the session of their own accord.

Invite

The Chat Properties dialog is initially used to select the Clients to include/exclude from the Chat session. To add Clients when the Chat session is in progress, click Invite. The Add Members dialog will appear, select the required Clients and click Add. You can send a copy of the Chat progress to new members by checking the **Send discussion history** box.

Note: Clients that have been removed or have decided to leave the Chat session can be invited back.

Eject

To remove Clients from the Chat session, select the Client in the Members list and click Eject. Ejected Clients can be invited back into the session if required.

Whiteboard

If required, you can introduce a 'Whiteboard' into the Chat session. This provides a range of tools enabling you to annotate the screen and display graphics.

Whiteboard Leader

If enabled, one of the participating Clients can be nominated to take control of the whiteboard.

Note: Clients can initiate Chat sessions with the Control by opening the Client Main Window and choosing {Commands}{Chat}.

Disable Chat Sessions

The Chat feature can be disabled in a Client's Configuration, preventing either the Client or Control from initiating a Chat session.

To Prevent the Control from Initiating a Chat Session

1. At the required Client workstation(s), choose **NetSupport Configurator** from the NetSupport Program Group. The NetSupport Client Configurator will appear.
2. Choose the Advanced Configurator option and select the profile to amend.
3. From the list of Configuration options select Security-Access Privileges.
4. Check the Disable Chat option.
5. Click OK.
6. Save the Profile and Restart the Client.

If the Control attempts to open a Chat session they will be advised that they do not have access rights to perform the task at that Client.

Note: To prevent the Control from Chatting to **all** Clients, disable the feature in the Control Configuration. Select Tools-Configurations-Settings from the Control Window drop down menu. From the list of Configurator options choose Control Interface-Functions and check the Disable Chat option.

To Prevent the Client from Initiating a Chat Session

1. At the required Client workstation(s), choose **NetSupport Configurator** from the NetSupport Program Group. The NetSupport Client Configurator will appear.
2. Choose the Advanced Configurator option and select the profile to amend.
3. From the list of Configuration options select Client Interface-Client Settings.
4. Check the Disable Chat option.
5. Click OK.
6. Save the Profile and Restart the Client.


The Chat option will be unavailable at the Client.

Sending Messages to Clients


With NetSupport, you can send a message to an individual Client, a Group of Clients or all Clients on the Network.

To send a message

1. Choose {Client}{Message} from the Control Window drop down menu.
or,
Click the Actions icon on the Control toolbar and choose Message.
or,
Right click and choose Message.
2. The Message dialog will appear. Choose whether to send the message to all Available Clients, All Connected Clients or only the Currently Selected Client. Enter the message and decide whether to show the message at Client PCs for a specified time.
3. Click Send.



The Message will be displayed in a dialog at the Client screens and will remain until the User closes the dialog or the specified time limit expires. In addition to the message itself, a customised Title can be included. This is set in the Control Configuration – General option. Click **Settings** on the Control Window toolbar.



Dealing with Help Requests


NetSupport Manager allows a User, at a Client workstation, to request help from a specified Control workstation.

If a Control's List View has been set to display Clients details {View}{Details} and customised to display help messages, the Clients help request message will be immediately displayed in the List View. The Help Request Folder in the Tree View will also turn green.

NetSupport Manager also allows you to configure Control workstations Help Request warning settings.

To adjust a Controls Help Request warning settings

1. Choose {View}{Settings for Current Configuration}{Control Interface - Help Requests} "When a Help Request Arrives" section.
2. A Control can choose to receive three additional warnings when a Client sends a help request message:
 - Have the Client selected in the List View;
 - Display an independent help request message on the Controls screen;
 - Play a sound when a help request message arrives.



A Control can also choose to be in one of three states of availability to receive Clients help requests.

To adjust a Controls Help Request availability

1. Choose {View}{Settings for Current Configuration}{Control Interface - Help Requests} 'Control Status' section.
2. A Control can choose from the following three settings:
 - Available to take all Help Requests
 - Unavailable to take any Help Requests
 - Busy at the moment (ensure that you specify the number of Clients you wish to be connected to, for this status to take effect)


When Browsing for Clients, Controls have the option to browse only for Clients who have requested help.

Capturing a Client's printed output

Print Capture redirects printer output from a local printer at the Client workstation to the printer or file at the Control. You would use this when running an application on a Client but want any printed output redirected to the printer that is local to you.

To redirect a Clients print output

1. Choose {Tools}{Configurations} from the Control Window drop down menus.
2. Select appropriate Configuration.
3. Click Settings.
4. Select Remote Control – Print Capture.



5. Check the Enable Print Capture box.
6. Select a printer to redirect the Clients output to. Either confirm that the current default is to be used or click Change to select another option.
Or,
Select a file to capture the print file to.
7. When you connect to a Client, a dialog is displayed informing you of the printer driver that has been used.

Notes

- In addition to enabling this option at the Control you also need to ensure that Print Capture is enabled in the Clients Configuration. The privileges are enabled by default.
 - Print output is captured only from the port to which the default printer is attached. Note that the Client may change this when Print Capture is enabled, as described above.
 - The Windows NT Client captures print output from DOS programs from the port to which the default printer is attached.
-

Remote Clipboard

During a View Session you can copy the content of the clipboard between Control and Client PCs.

The Clipboard icon, available on the View Window Toolbar, provides the following options:

Send Clipboard

Used when copying from the Control to a Client and using the {edit}{cut/copy} menu option.

Retrieve Clipboard

Used when copying from the Client to the Control and using the {edit}{cut/copy} menu option..

Auto

When enabled, provides the quickest method for copying data. Use the short cut keys (Ctrl-C & Ctrl-V) to automatically copy to and from the clipboard at both the Control and Client machines.

Sending the content of the clipboard from a Control to a Client workstation

1. View the required Client.
2. Open appropriate applications on the Client and Control workstations.
3. Select and copy the required data from the application at the Control.

If **Auto** is enabled using Ctrl-C copies the data directly to the clipboard.

or

If you have used {Edit}{Cut/Copy}, return to the Clients view window and click the Clipboard icon on the View Window toolbar and choose Send Clipboard.

4. To paste the data at the Client application, choose {Edit} from the Client application drop down menu, select Paste.

or

Use the short cut keys (Ctrl-V) to paste the data.

Sending the content of the clipboard from a Client to a Control workstation

1. View the required Client.
2. Open appropriate applications on the Client and Control workstations.
3. Copy the required data from the application at the Client as above but if using menu options rather than the shortcut keys, choose Clipboard – Retrieve Clipboard from the toolbar.
4. Return to the Control application and paste the data using the appropriate menu options or the short cut keys (Ctrl-V).

Integration With Explorer

NetSupport Manager integrates directly with Windows explorer, allowing you to launch key functionality direct from your system without needing to first start the NetSupport Control.


By selecting a PC icon from within Network Places/Neighborhood you can establish a remote session and perform a range of common tasks.

Notes:

- The functionality is only available if the NetSupport Control component is installed.
- A Remote Control session will only be established if the target machine is running a NetSupport Client and the Client Name is set to the default Machine Name.

To use NetSupport Functionality from within Explorer

1. Open Explorer from your desktop and navigate to Network Places/Neighborhood to find the list of available PCs.
2. Right-click on the required PC.



3. Select the appropriate NetSupport function. You can choose:

Remote Control To view the selected Client screen.

Chat To open a Chat session with the selected Client.

Inventory To retrieve a full Hardware/Software Inventory of the selected PC.

To disable NetSupport Functionality


If required, NetSupport Explorer functionality can be disabled in the Control Configurator.

1. Select **{Tools} {Configurations}** from the Control Window drop down menu.
2. Select the Control Profile to apply the changes to.
3. Choose **Settings**.
4. From the Configuration Settings dialog, choose **{Control Interface – Settings}**.
5. Check the **Disable Shell Extension** box.

Remote Command Prompt

By launching the Command Prompt Window a Control can remotely execute command line instructions at a connected Client.

1. Connect to the required Client and choose {Client}{Remote Command Prompt} from the Control Window drop down menu.
or
Right-click on the Client icon and select Remote Command Prompt.
or
Click the Actions icon on the Control toolbar and choose Remote Command.
2. The Remote Command Prompt Window will appear. The title bar will confirm the name of the connected Client.



The Window is split into two frames. The Input Frame at the bottom of the window, which can be resized if required, and the output/results frame at the top.

A range of tools are available via the drop down menus and toolbar enabling you, for example, to clear the output window and change the displayed font.

Using the Client

In this chapter ...


How the remote user can interact with a connected Control.

The Client Main Window

When a Client double clicks on the NetSupport icon on their task bar or presses the hotkeys Alt-LShift-RShift, the Client Main Window appears.

From here a Client can:

- Initiate a Chat session with a Control;
- Request Help from a specific Control;
- Call a specific Control;
- Connect or Disconnect from a Control;
- Launch a Replay File – See 'Watching Recorded Replay Files'
- Switch Desktops;
- Load or Unload a Bridge.



Connecting to a Control

The Client Connect function only works for TCP/IP connections and is intended to enable you to establish a connection across a Firewall or Proxy Server.

Note: To enable a Client to call a Control, NetSupport uses TCP/IP port 5421. For the Client to connect through a Firewall, you will need to configure the Firewall to use this port.


To connect to a Control

Note: The Control must be running for a Client to connect.

1. Choose {Commands}{Call Control} from the Client Main Window drop down menus.
2. The Call Control dialog appears.
3. Enter the hostname or IP address of the Control you wish to connect to.
Or,
Select from a list of the 10 most recently connected Controls.

Note: A maximum of 10 Controls can be stored, after which the oldest is discarded.

The Control will receive a connecting message and either allow or disallow the connection. If the connection is disallowed, the Control and Client will be able to behave as normal.



Disconnecting from a Control

To Disconnect from a Control

1. Bring up the Client Main Window and choose {Commands}{Disconnect} from the drop down menu.
Or,
Right click on the Client icon in the Taskbar's system tray.
2. When the short cut menu appears, choose the Disconnect command.
3. A dialog box will appear, listing the Controls to which you are currently connected.
4. Select the Control(s) from which you want to disconnect.
5. Choose OK to disconnect from the selected Controls.

Raising a Help Request

NetSupport Manager allows a User, at a Client workstation, to request help from a designated Control workstation.

To Request Help

1. Choose {Commands}{Request Help} from the Client Main Window drop down menu.
Or,
Clients press the Hot Keys, usually ALT+LSHIFT+RSHIFT.
2. This opens a dialog box into which Clients type their name and help request message.
3. Clients can then specify which Control workstation they wish to send their help request message to, by clicking on Show Control and selecting a Control workstation.
4. Clients can also choose to Cancel their previous help request by clicking Cancel Previous Request.
5. Clients then click OK.

If a Control is connected when a Client sends a help request, the Help Request Folder will immediately turn green. If the Control is not connected, its Help Request Folder will turn green the next time it connects to that Client.

Chatting to a Control workstation


You can Chat to a connected Control using the Chat Window.

To initiate a Chat session

1. Choose {Commands}{Chat} from the Client Main Window drop down menus.
2. The Chat Window will appear.
3. Type the message and hit Enter or click **Send**.
4. If you need to alert the Control User that you have initiated a chat session, choose {Chat}{Send Beep} from the Chat Window drop down menus.

Receiving Messages from a Control workstation

Client workstations can receive messages from Control workstations. These messages are automatically displayed on a Client's screen in a message box.



The message box's title bar includes the name of the Control that has sent the message, along with the date and time the message was sent.

Having read the message sent by a Control, choose **OK** to remove the message.

Resetting the Client Video Driver on Windows 95/NT4

This procedure may be necessary if you install a new video display adapter or in Windows 95 Clients when you have changed the display settings.

Note: When using Windows XP/ME/2000/98 the Client will automatically reset the video driver, if required, when the Client starts.

In Windows 95 the video driver can be stored in the SYSTEM.INI or the registry, in NT the video driver is stored only in the registry. The default is SYSTEM.INI, however when you reset the video driver you can change where the information is stored. If you choose to store the information in the SYSTEM.INI file then you may need to reset your video driver when you change screen resolution or other video driver settings.

To reset the Client Video Driver

In Windows NT

1. Choose {Start}{Programs}{NetSupport}{Reset Video Driver}.

In Window 95

1. Choose {Start}{Programs}{NetSupport}{Reset Video Driver}.
2. Select a location to store the NetSupport Manager display drivers.

Configuring the Client

In this chapter ...

How to use the Client Configurator.

Whether you want to secure the Client against unwanted connections or prevent Control Users from performing certain tasks at selected Clients, NetSupport Manager provides a vast range of configuration options that can be set at individual Client level.

Configuring the Client

NetSupport Clients are configured using the NetSupport Configurator. This makes all the required changes to and sets up the initialisation commands.

The Configurator is started from the NetSupport Configurator Icon in the NetSupport Manager Program Group. This will display the initial Client Configuration dialog.

You can also load the Configurator from the command line by entering the appropriate parameters. For example, "c:\program files\netsupport manager\pcicfgui.exe. If School Components have been installed, you can load the NetSupport School Client Configurator by entering, "c:\program files\netsupport manager\pcicfgui.exe" /s.

Note: When performing a custom installation, the Configurator Component must have been selected for this option to be available.

The Client Configurator enables you to set all the possible options for the Client. It also enables you to test the Network to ensure that the Network stack that you are attaching the Client to is installed and operating correctly.

You can run the Configurator in two modes, *Basic* or *Advanced*. Some of the options are accessible in both modes.

Basic Client Configuration

Basic Configuration is used for standard settings such as the Client Name, the transport(s) that it will use and simple security such as password and security keys.

Note: Basic Client Configurations can also be set as part of the NetSupport installation process.

Choose this option if:

- You are using the Client Configurator for the first time.
- You only wish to set simple security and configuration options.
- You do not need to create multiple profiles for different Control Users who might connect to this workstation.

Note: Do not use the Basic option if you have set up multiple profiles using the Advanced Option, as this will also change the Master Profile in the Advanced Configuration.

Advanced Client Configuration

The Advanced option provides access to NetSupport's wealth of configuration and security options. It lets you tailor the response of the Client to different Control Users who may access the workstation and provides links to areas such as NT Security.

Note: When performing a custom installation, the Configurator Component must have been selected for this option to be available.

Choose this option if:

- You are an experienced User.
- You need the Client to react differently depending on which Control User is connecting.
- You wish to enable/disable individual features.
- You want to link to NT Security.
- You want to restrict a Control User's access to specific drives, directories or files.

Note: Any changes you make to the Master Profile in the Advanced option will overwrite any setting that you have made using the Basic option.

Editing or creating Configuration Files


Choosing the Advanced Option from the Client Configurator creates configuration files. This will display the Advanced Configuration Window.

The default Configuration file is called CLIENT32.INI and is stored in the NSM installation directory of the Client workstation. You can use either this file or a different file on a Server to which the Client has access.


Note: Once created, a Configuration file can also be remotely deployed to multiple Client machines simultaneously using the NetSupport Deploy utility.

To create a new Configuration File

1. Choose **NetSupport Configurator** from the NetSupport Program Group. The NetSupport Client Configurator will appear.



2. Choose Advanced. The NSM Client Configurator dialog will appear.



3. Choose {File}{New} from the Advanced Configuration Window drop down menu bar.
4. A new file will be created with a Default master Profile.

To open the default or an existing Configuration File

1. Choose {File}{Open} from the Advanced Configuration Window drop down menu bar.
2. Select the Configuration File you want, click Open.

To set the Configuration file the Client will use

The configuration file that the Client uses when it initialises can be on the same workstation or on another workstation or Server to which that workstation has access. Multiple Clients can share the same configuration file for ease of Administration. The Configuration file to use is set by choosing {Profiles}{Client Parameters} from the Advanced Configuration drop down menu bar.

Note: There are special requirements for setting Windows Me/98/95 Clients to use shared configuration files on an NT/Windows 2000/XP workstations.

To Set the Client Name

1. Choose {Profiles}{Client Parameters} and insert a Client name.

Note: The Client name is separate from the Configuration file and is stored on the local workstation. Make sure that you do not choose the same Client name as is used on another workstation. Setting the Client name to be an asterisk is a useful strategy, as the Client name will then be set to be the same as the Computer Name. The Computer Name should always be unique.

To create a new Profile

1. Open or create the Configuration file you want to use.
2. Choose {Profile}{Add} from the Advanced Configuration Window drop down menu bar.
3. Enter the name for the Profile.

Note: You can combine Profiles from other configuration files by choosing the "Include File" option. This is useful where you are using Configuration files on the local workstation but want to include information stored on a central configuration file or vice versa. For example, if the local workstation was using a different NetBIOS Adapter number. Each Profile contains a number of Property Sheets where the actual parameters are set.

To edit an existing Profile

1. Open or create the Configuration file you want the Client to use.
2. Select the profile you want to Edit.
3. Choose {Profile}{Edit} from the Advanced Configuration Window drop down menu bar.
4. Edit the profile.

Note: If you leave the check boxes greyed, the settings from the Master Profile will be used.

Basic Client Configuration

For use in a simple environment where you do not require the Client to react differently according to the Control User connecting to it and do not need to enable/disable individual functions.


To open the Basic Client Configurator

1. Open your NetSupport Manager Program Folder by choosing {Start}{Programs}{NetSupport}{NetSupport Configurator} from your operating system menus.

Or,

Double click on the Configurator icon in the NetSupport Group.

2. Select Basic. The Basic Client Configurator covers three areas:
 - Connectivity
 - Security
 - Audio



Advanced Client Configuration

The NetSupport Manager Client is exceptionally configurable and supports the ability to set differing levels of security and response according to the identity of the Control User that is connecting. This is achieved by the use of configuration files at the Client, which determine the appropriate level of access for each Control User by means of a Profile.

It is important that the concepts behind Configuration Files and Profiles be fully understood.

Configuration File

A Configuration File is a Text File, consisting of sections called Profiles.

You can specify the Configuration File that the Client will use when it initialises. The Configuration files themselves are stored in a check-summed file, normally Client32.Ini.

This file can be either on the Client workstation or on another workstation such as an NT Server to which the Client workstation has access. You can even set the Client to use a fallback configuration file in case the Server is unavailable.

Note: There are special requirements for setting Windows 9x workstations to use shared configuration files.

Profile

A profile is a set of parameters that determine how the Client will respond to a particular Control User and what functionality they will allow that Control User to have.

For example, one Control User may be allowed to View the Client in Watch only mode while another may be allowed full functionality including File Transfer. You can even set up the profile to pre-determine exactly what file access a Control User will have.

A profile set at the Client overrides a profile set at the Control. Security is therefore always ensured.

When connecting to a profiled Client, the Control User will be prompted for a UserID and a Password. The NetSupport Client will then interrogate the first matching Profile in its current configuration file to determine what level of functionality has been assigned to that Control User.

Master Profile

Each configuration file must contain a Master Profile. This is the standard profile and is the one used if you only set a Basic Configuration. Whatever is set here will, by default, apply to all other Profiles you create.

However, you can then amend those profiles to enable or disable particular features for Control Users whose USERID and password match those set in the Profile.

As the Master Profile is the first one that the Client checks you should always set maximum security features here to avoid leaving a security back door open.


The Master Profile is also used for setting a number of Global Parameters that apply across all individual Profiles.

Individual Profile

An individual profile allows you to enable or disable individual features for a particular Control User or Group of Control Users. When they connect, the Client will prompt them for a User Name and Password. It will then search its internal profiles until it finds a match and then apply the settings to the subsequent Control session.


The Advanced Client Configurator covers five areas:

- Connectivity
- Security
- Remote Control
- Client Interface
- Profile Options




Connectivity Options

These property sheets are used to set which protocols the transport will allow a Control to connect to it by. The NetSupport Client supports multiple protocols meaning that you can set it up to respond to NetSupport Control's whether they are talking over TCP/IP, IPX or NetBIOS. You can also configure the Client for remote communication via a modem or establish a connection through a NetSupport Gateway. The gateway provides a method for connecting via http and delivers web based remote control without the need for modifications to existing Firewall configurations.



Set TCP/IP Connection



Use TCP/IP

Check this box if you wish the Client to be able to communicate over TCP/IP.

Port

The TCP/IP protocol requires that a port number be allocated for applications to communicate through. To enable the Control to communicate with a Client, and for the Client to receive the incoming request, the default registered port for NetSupport is 5405.

Select IP Address to Listen on:


This option can prove useful for preventing unwanted connections when the Client has multiple network cards installed, for example, when both a public and private network are used. You can force connections on the required network by specifying the IP Address that the Client uses to listen for incoming Control connections.

Press [**TEST**] to check that the protocol is correctly installed on this workstation.

Notes

- Changing port could interfere with other TCP/IP applications.
 - If you are using Routers, you must ensure that they are configured to pass through data using this port.
 - To enable Clients to initiate a connection to the Control, the default registered port is 5421.
-


Set IPX connection



Use IPX

Check this box if you wish the Client to be able to communicate over IPX/SPX. Press **[TEST]** to check that the protocol is correctly installed on this workstation.

Set NetBIOS connection



Use NetBIOS

Check this box if you wish the Client to be able to communicate over NetBIOS/NetBEUI. If you are using NetBIOS, you must also select a NetBIOS Adapter Number. Press **[TEST]** to check that the protocol is correctly installed on this workstation.

Adapters (select one or more)

As you can have more than one NetBIOS stack loaded, Windows uses the concept of Adapter numbers. Each stack is allocated an Adapter number by the operating system. So for example, NetBEUI may be allocated Adapter 1, NetBIOS over TCP, Adapter 2 and so on.


By default, the Client uses Adapter number 0. Depending on how your Network is configured this may not be the correct Adapter number for your workstation. To overcome this you must select the required stack from the drop down list.

Notes

- NetSupport allows you to select multiple NetBIOS Adapters. Make sure only the ones you want are selected. If changing the selected adapter, make sure that you first de-deselect the existing or default adapter number.
 - Under Windows 95, changing you Network settings may also change the NetBIOS adapter number. You may need to re-set the NetBIOS adapter number NetSupport uses after such a change.
-

Set HTTP connection

This property sheet enables you to configure the Client to accept connections via a NetSupport Gateway. (For more information see, [Connecting to Clients/Controls via a NetSupport Gateway](#))



Use HTTP:

Check this box to enable the Client to communicate over HTTP.

Gateway Address:

Enter the IP address of the workstation where the NetSupport Gateway Component is installed.

Secondary Gateway (optional):

If required, enter the IP address of the secondary Gateway.

Port:

NetSupport's default port for HTTP communications is 443.

Note: In version 9.10, Port 443 was introduced as the default for HTTP communications, 3085 being used previously. Gateway settings will be preserved for existing customers who subsequently upgrade, enabling 3085 to continue to be used, but there may be scenarios when upgraded Controls and Clients will need the HTTP Port manually reconfiguring to ensure compatibility.

Gateway Key:

The Key set here **must** also be set at the Control and match the key that has been configured in the Gateway itself. Provides additional security that enables Control Users to connect only if they have specified the same key as at the Client.

CMPI (secs):


You can override the CMPI that is set at a Gateway by entering a value here. By default at the Gateway the CMPI is set to 60 secs.

Proxy Server

NetSupport can be configured to route communications through a Proxy Server if required. Enter the server address and an appropriate Port, 8080 recommended.

Dialin Bridge Settings

This property sheet is used to set up Dial-in NetSupport links either to this workstation or to any NetSupport Client on the same LAN as this one.



Protocol

By default, NetSupport Manager is set to have no transport for the Bridge selected. Choose to use either the NetBIOS, IPX, TCP/IP protocols for NetSupport Bridge.

Bridge Options

Load Bridge on Startup

Setting this option will cause the NetSupport Bridge to initialise when the Client loads. If you do not set it then the User at the Client must load it manually from the menu on the NSM Client before dial-in access will be available.

Inactivity Timeout

Specify, in minutes, a maximum time span of inactivity at the Bridge before the Control disconnects.

Dialback File

You can set up the Bridge to support both passwords and dialback with the additional functionality of dialing back different telephone numbers according to the password.

Modem/ISDN

You must select a modem, from the list of modems installed in the Control Panel of the workstation, for the Bridge to use.


Dual Channel Bonding

If enabled, both channels of your ISDN line are combined thus increasing the amount of available bandwidth to 128k. However, in increasing the speed of transmission you are in effect making two calls.

MSN (Multiple Subscriber Number)

Specify a number that you want the bridge to accept incoming connections from. Depending on the channels in use, you need only specify the trailing digit(s). For example, if the ISDN lines in use are 0181 123456 and 0181 123457, specify 6 or 7.

Advanced Setting



Tickle period

While a Control is connected, the Client sends Tickle packets to the Control to verify that it is still “alive”. You might like to disable tickle packets for ISDN links but be aware that the Client may then not detect that the Control has disconnected unexpectedly.


The normal period between tickle packets is 18 seconds but you can increase or decrease this value. Setting this to zero disables tickle packets entirely.

Auto configure for XP SP2 firewall

Enabled by default, ensures that the NSM Control and Client continue to function for those users who upgrade to XP Service Pack 2.

Web Extensions

This property sheet allows you to configure the Client to act as a simple Web Server. The TCP/IP transport must be enabled for this to work.



Enable Web Extensions

When this is checked the Client is able to act as a simple Web Server. Typically, you would enable this to allow you to access the Client via the Internet, using the Integrated Browser. See on line help for details.

Server Port

The Server Port number is set, default, to 80. You may want to change this for security reasons.

Server Root Directory


The server root directory is set to where you have installed NetSupport. You may wish to change this for security reasons.

Security Options

These property sheets are used to set security at the Client.

General Settings

Used to set passwords to protect the Client configuration and to prevent unauthorised access to the Client.



Identification

Client Name

Each NetSupport Client on the Network requires a unique name. You can either set a name of your own choosing or use an asterisk to default the Client name to be the same as the workstation name.

On NT you need to be logged in as Administrator to change the Client name.

Note:

- If setting the Client Name in Advanced Configuration choose {Profiles}{Client parameters} from the Advanced Configuration Window menu bar.
 - In order for NetSupport's Integration with Explorer feature to work, the Client Name must remain set to the default Machine Name.
-

Configurator Password

As an extra level of security, you can associate a password with a Configuration File. This prevents unauthorised amendment of this Client's configuration. When the Configurator is next started, the user must enter the required password before being able to change any client parameters in this Configuration file. Choose Set, to set your password.

Client Password

This helps to protect the Client from unauthorised access from a NetSupport Control. The Control user will be required to enter the password before obtaining access to the Client.

Client Security Key


Provides additional security that enables Control Users to connect only if the Control has the same security key as the Client. Optionally this can be set as the Serial number. You must set the Security key at both ends.

Quiet Mode (Client not visible on Taskbar)

Check this box to hide the Client icon on the Taskbar.

Access Privileges (Basic)

This property sheet can be used to limit the range of Remote Control options that are available to the Control User.



User Acknowledgement Required

Prevents access to the Client unless a user is present. The user at the Client will have to explicitly accept the request to connect before access is granted.

Disable File Transfer

This prevents a Control operator from being able to transfer files to and from the Client. The Control user will not be able to copy, view or otherwise manipulate files on the Client using the NetSupport Control file transfer options.

Disable Execute

This prevents a Control user from remotely executing applications at the Client from within the menu option in the Control program. They can still start applications on the Client while remote controlling the workstation.

Disable Remote Registry Access

A Control user can remotely manage and edit the Registry on NetSupport Clients. Setting this option will disable that function.

Watch Only

Enables the Control user to be able to view the screen of the Client workstation but prevents them from being able to enter keystrokes or mouse movements.

Disable Receive Show


Prevents the Client workstation from being able to display a Show sent by a NetSupport Manager Control.

Disable Remote Reboot

This prevents a Control user from being able to remotely reboot the Client from the Menu option in the Control Program.

Access Privileges (Advanced)

This property sheet can be used to limit the range of Remote Control options that are available to the Control User.



Disable Watch

Prevents a Control from Viewing the Client at all. File transfer, scripting and other functions are still available.

Disable Share

Allows a Control to View a Client in Watch only mode.

Disable Control

Prevents a Control from being able to lock out the Client's keyboard and mouse.

Disable File Transfer

Disables File transfer to and From the Client in all circumstances.

Disable Execute

This prevents a Control user from remotely executing applications at the Client from within the Control program. They can still start applications using the standard Remote Control functions.

Disable Reboot

Disables the ability of the Control User to Re-Boot the Client workstation via the menu option in the Control Interface. You can still Reboot while remote controlling.

Disable Shutdown Client

Prevents the User at the Control from being able to shut down the Client program from a script.

Disable Chat

Prevents the Control from initiating a Chat session with the Client. However, Clients can still open a Chat session with the Control via the Client Menu.

Disable File Transfer when no NT User is Logged on

Disables File Transfer only if it is an NT workstation and no user is logged on. This means that the Control user could log on as with their own User ID if they have a valid User ID and password for this workstation.

Disable Remote Command Prompt

Prevents the Control from being able to run Command Line instructions at the Client.

Disable Blank Screen

Prevents the Control user from being able to blank the Client screen.

Disable Ctl+Alt+Del

Ignore Ctrl+Alt+Delete sent from the menu option in the Control Interface.

Disable Logoff

Disables the ability of the Control User to log off from the Client workstation via the menu option in the Control Interface. You can still Log off while remote controlling.

Disable Clipboard Access

Prevents the Control user from being able to use the Remote Clipboard.

Ignore Messages

Ignores messages sent by Connected Controls.

Ignore Broadcast Messages

Ignores Broadcast messages from a Control whether connected or not.

Disable Print Capture

Prevents the Control user from being able to use NetSupport's printer re-direction function.

Disable Registry Access

The Script function and later versions of NetSupport Manager include a function to enable a Control user to remotely manage and edit the Registry on NetSupport Clients. Setting this option will disable that function.

Inventory

These options are disabled by default, un-check to enable the facility. If enabled, the following tasks can be performed when viewing the Hardware/Software Inventory of a selected Client.

Note: If a Client is not selected, the task will be performed at the Local machine.


Disable Close Applications

If checked, prevents the Control being able to close a currently running Application or Process.

Disable Service Management

If checked, prevents the Control being able to stop or start a Service at the Client machine.

User Validation



Usernames

Usernames are used for setting the valid USERID and Password for Control Users when they connect to the Client. The USERID is also used to determine which Client Profile will be applied.

You can enter multiple USERNAMES each with its own password. You do this by clicking on Change and adding the individual UserNames and passwords.

By entering specific Usernames and Passwords the Client will restrict access to Controls entering a matching Username and Password when connecting.

Notes:

- If this is an NT workstation and you have elected to use the NT Security option to validate the Control Users ID and password then you do not need to specify the Username and Password. However, you may still wish to set this option to provide an additional filter when using NT Security validation to restrict access to particular NT Users and determine which Client profile they will use.
 - Rather than continually prompt the Control User for a username, a default ID can be set in the Control Configuration - General settings.
-

NT Options

Authenticate User and Password with NT

This only applies to NT Clients. If this option is set then the UserID and Password entered at the Control must be a valid NT ID on the Client workstation or its default domain.

Restrict Access to members of the following groups

You can further restrict access by specifying groups. Click on Browse to select a group(s).

Active Directory Options

If in use you can configure the Client to validate a user connection against members of the groups defined within Active Directory. A connecting Control will be prompted for their USERID and Password which will be validated against the Active Directory.

Restrict Access to Members of the following Groups:


As an additional level of security you can restrict access to members of specified groups.

Always Prompt for Username and Password

If checked, the Control will be prompted for a username and password each time it attempts to connect to the Client.

User Acknowledgement Options

These security options, when enabled, display a prompt at the Client machine advising that a Control User is attempting a remote connection. The Client must acknowledge the message before a remote control session can be instigated.



User Acknowledgement

User Acknowledgement Required

When a Control User attempts to connect, a message will be displayed at the Client. Unless the user at the Client explicitly accepts the request, the connection will be refused.

Except when no NT User Logged ON

Only applies when User Acknowledgement has been set. This means that the Client can be configured to allow remote control when the workstation is at the log in screen. The Control User would have to have a valid ID and Password to be able to log in.

Acknowledge Connection Attempts from other Controls

The Client receives a message that another Control is attempting to connect.

Acknowledge Connection Timeout:

Specify a time limit, between 0-255 seconds, for the User Acknowledgement prompt to be displayed. If the Client has not responded to the message within the specified time the connection attempt will be rejected.

Acknowledge Connection Display:

Specify a customised acknowledgement message to be displayed at the Client workstation. The text can also incorporate a choice of default settings should you wish the Client to know, for example, the name of the Control User. There are four available syntax's:

\$loginname\$	Returns the logged on user name of the user at the Control.
\$fullname\$	Returns the full name of the logged on user at the Control.
\$computername\$	Returns the machine name of the Control.
\$userdomain\$	Returns the domain of the logged on user at the Control machine.

Note: The standard NetSupport Graphic in the User Acknowledgement Dialog can be replaced with a customised Graphic by placing an Icon file with the name helpdesk.ico in the installed directory for the product on the client machine.


View Acknowledgement

Acknowledge switching to xxxxx view mode or higher.

Displays a prompt at the Client machine if, while being viewed, the Control User wishes to switch to a higher View Mode. For example, if the level is set to 'Control', the prompt will appear if the mode is changed from Share or Watch. The Client can choose to Accept or Reject the change.

Connect Options

This property sheet is used to administer which Control Users or Control workstations can connect to this Client. You can also set the level of encryption to be used.



Security Key

Provides additional security that enables Control Users to connect only if the Control has the same security key as the Client. Optionally this can be set as the serial number in your NetSupport Licence File. You must set the Security key at both ends.

Allow Connections from these Control Machines

This enables you to restrict access to Controls running on IPX or TCP/IP networks. This feature can also be used to limit access to Control workstations with specific addresses. Wildcards can be used in the address field.

For example:

194.182.*.* all workstations on TCP/IP subnet 194, 182
00000001-* all workstations on IPX network 1

Encryption

With encryption turned on, all the information that is sent between the Control and Client is very difficult for others to read. NetSupport offers a range of encryption options, ranging from 56 Bit DES to 256 Bit AES, enabling you to find the necessary balance between security and performance. The higher the level of encryption, the higher the potential for decreased performance

Force Controls To Use Encryption

Checking this box forces a connecting Control to use the equivalent level of encryption, even if the option has not been enabled at the Control end. The encryption only applies when the Control is connected to this Client.

Set Minimum level of Encryption


Choose the level of encryption to be used while a Control is connected.

Allow more than one Control to connect at a time

NetSupport allows multiple Controls to connect and view the Client simultaneously. This is useful for Group Working. Checking this option enables the function.

Disconnect Options

The options on this property sheet provide additional security when a Control User disconnects from the Client machine. Particularly useful if the connection to the Client is unexpectedly lost.



Lock the workstation if not initially logged on – NT only

When the Control user disconnects the workstation will be locked. The Control user will be able to re-connect and unlock the workstation. This option is valuable when the Control may unexpectedly loose the Connection. It prevents a user at the workstation inheriting the Control users rights, (assuming they have logged in as an Administrator for example). This only applies if the workstation was logged off when the Control was connected.

Logoff if not initially logged on

When the Control user disconnects, the workstation will be automatically logged off. This only applies if the workstation was logged off when the Control connected.

Restart if not initially logged on

When the Control user disconnects the workstation will be automatically restarted. This only applies if the workstation was logged off when the Control connected.

Logoff if user has changed

If a Control needs to logon to a Client workstation under a different name to the user, for example as an Administrator, it prevents the user inheriting the Control users rights should the connection be unexpectedly lost.


Disconnect Display Text

Specify a customised message to be displayed at the Client workstation when a Control disconnects. The text can also incorporate a choice of default parameters should you wish the Client to know, for example, the name of the Control User. The available options are:

\$loginname\$	Returns the logged on user name of the user at the Control.
\$fullname\$	Returns the full name of the logged on user at the Control.
\$computername\$	Returns the machine name of the Control.
\$userdomain\$	Returns the domain of the logged on user at the Control machine.

Protect Configuration Settings

This property sheet allows you to protect the Client Configurations.



Configurator Password

Nominate a Security Password for the Client profile.

Authenticate User and Password with NT

This only applies to NT Clients and therefore only protects Client Configurators on NT workstations. If this option is set, the UserID and Password entered at the Control must be a valid "Act as part of the Operating System" NT ID on the Client workstation, or its default domain. This User Right is not granted by NT as default.

To grant this User Right

1. Run {Programs}{Administrative Tools}{User Manager}.
2. Select {Policies}{User Rights} from the drop down menus.
3. Check the "Show Advanced User Rights" check box.
4. Select the Right.
5. Click on Add.
6. Select which users and/or groups, this right should be granted.
7. Click on OK.
8. For this User Right to be recognised you must relog into your workstation.


Note: You can also point the Client to validate the ID in another Domain.

Restrict Access to Members of the following Groups

You can further restrict access by specifying groups. Click on Browse to select a group(s).

File Transfer Settings

This property sheet is used to control file access.



Disable File Transfer

Disables File Transfer to and from the Client in all circumstances.

Disable File Transfer when no NT user is Logged on

Disables File Transfer only if it is an NT workstation and no user is logged on. This means that the Control user could log on as themselves if they have a valid User ID and password for this workstation.

Impersonate Logged on NT User when Transferring Files

When using NetSupport file transfer, the Control User will have the same file access as the Logged on user.

Access Rights to Directories and Files


This is used to explicitly allow or deny access to individual Drives, Directories and Files. Note that it only applies to File Transfer within NetSupport Manager.

It is hierarchical in nature so you could for example disable access to Drive C:\ in general but explicitly grant access to sub directories.

Note: Any Access Rights set in the master profile applies to all profiles, unless overridden.

Replay File Settings

The Replay Files feature enables the Control to record and playback the screen activity that takes place at a Client workstation while it is being remote controlled/viewed.



Record Replay Files

Check this option to enable the recording of Replay Files. A Replay File will be created each time the Control views a Client PC with the option enabled.

Prefix Files With Client Name

In order to identify each Replay File, filenames can be prefixed with the Client Name and the date/time of the recording. Alternatively, with the option un-checked the files will be named sequentially in the format 00000001.rpf etc.

In Directory


Specify where the Replay Files should be stored. If saving to a Network share this gives you the opportunity to store each Clients files in individual directories.

As User

The user name and password used to write to the log file.

Event Logging

Log files record the activity that takes place at a Client machine while it is being remote controlled. Standard information would include the name of the Control that had initiated the connection and the date and time that the session started and ended. The text files that are created provide a useful audit trail but you can also enhance Client security using this feature.



Enable Logging

Check this box to enable logging.

Log to NT Event Log

Sets the Log to be maintained within the NT Event Log.

Log to File

Sets the Log to be maintained within a text file. This file can be on the Local workstation or on a Server. Multiple Clients can write to the same Log file.

Primary Log File

Specify the path, and file name (*.log), where the log file will be stored.

Secondary Log File

Specify the path for a Secondary log file. In the event that the Primary path cannot be found, for example the server is down, the file will be stored here.

Notes

- To make the tracking of log files easier, particularly if multiple Client log files are stored on the same server, the file names specified above can include the Clients computer name and the date that the log was created. For example: \\Logserver1\logfiles\%computername%dd\$mm\$yy\$.log. In this instance you would be able to build up a daily record of activity on a particular Client machine.

Acceptable formats for the date are:

dd\$mm\$yy\$ which for 18th September 2003 returns 1893.

dd\$mm\$yy\$ returns 180903.

ddd\$mmm\$yyy\$ returns ThuSep2003.

ddd\$dd\$mmm\$yyy\$ returns Thu18Sep2003.

dddd\$dd\$mmmm\$yyyy\$ returns Thursday18September2003.

- For NT/2000/XP, this file must be a UNC path name as a mapped drive is not available until you log in.
 - For Windows 95/98/ME, the file must be in a Null Session Share.
-

As User

Log File User is the user name and password used to be able to write to the log file when the path specified is a UNC Path.

Append to File

By checking this box, NetSupport will continually add to the existing entries in the log file. If unchecked, existing items get overwritten.

Reject Connection if no Log Server available

By enabling this option you can apply additional security. With logging enabled, if a Control attempts a connection and neither of the Log Files can be found the connection request is rejected. This ensures that any audit checks that you may have in place will not be compromised due to the activity not being logged while the servers are down.

Only Log while Connected


This option ensures that activity is only logged during the period that the Control is physically connected. When logging is enabled some additional information is recorded that you may prefer to ignore, Client configuration data for example.

Note: Another useful item of information that can be recorded is the reason why a Control connected to the Client. This comes into effect when 'User Acknowledgement ' is enabled at the Client machine and the Control Security Settings option is configured to 'Prompt for additional information when connecting'.

Remote Control Options

The following Remote Control attributes can be adjusted:

View Settings



Options

Send Physical Fonts

When a Windows Client is sending its screen to a Control, it passes the font information by reference to reduce the volume of data sent.

The Control refers to its own internal font mappings and uses the closest matching that it has to the one being displayed at the Client. In most cases, the same fonts will be available at both the Client and the Control and so what is displayed on the screen will appear identical.

However, there may be occasions when a close match cannot be found. In these cases, it is desirable that the Client sends the Control the full information that it requires to display the data in the same font.

Setting this option forces *TrueType* text to be sent as glyphs (i.e. character shapes), rather than character codes. This guarantees that they will be displayed correctly at the Control.

This will, however, impact on performance, especially on Dial-up lines, and is not usually required.

Enable Screen Scrape

NetSupport's favoured, and the most efficient, method for capturing screen data is to hook into the Video Driver of the workstation being viewed.

However, there may be occasions when this method will not work because certain applications bypass the driver. In these circumstances you can enable 'screen scrape' mode in order to take a snapshot of the screen. Although this will have a greater impact on the network it will at least provide an accurate representation of the Client's screen.

Cache Size

Screen data that has been recently sent to the Control by the Client is cached to improve performance. A larger cache improves performance, at the expense of using more memory at both the Client and the Control.

Setting this option enables you to tailor the cache size used for maximum performance. The lower of the cache size set at the Client and Control will be used so you must set at both ends for this to be effective.

You can determine how efficiently the cache is working by selecting {Help}{About}{Cache} from Client View Window at the Control. This will display statistics of hits etc.

Max Colour Depth

The higher the colour depth at the Client the greater the volume of data that needs to be sent to the Control for each screen update. Restricting the Colour depth will improve performance on slower links.

Note: The settings here will override the colour depth setting in the Control Configuration.

Inactivity Time Out

When a Control connects to a Client, it can prevent other Controls from connecting to that same Client, unless the Allow Multiple Connections option has been set.

If the operator at the Control forgets to terminate the connection then a case might arise where other Control operators who need access are locked out.

Setting this option means that if a connected Control has not carried out any mouse, keyboard or file transfer activity for the specified period, the Client will assume that the connection is no longer required and disconnect automatically. It will then be available to other Controls.

Enable DVD Playback and Direct 3D support (Win 2000/XP Only)

On Windows 2000 and XP, NetSupport uses the Microsoft Mirror Driver to capture screen data for view sessions. However, while hooked into the Mirror Driver it is not possible to play DVD's. Therefore, if you do need the capability to play DVD's, NetSupport provides options which load and unload the Mirror Driver as required.


Except While Viewed

If checked, DVD support is enabled but will be disabled for the duration of a view session while the Mirror Driver is loaded.

Except While Connected

If checked, DVD support is suspended while a connection to the Client is in place.

Show Settings



Receive Show Options

Disable Receive Show

Prevents the Control from being able to show to the Client.

Show to a Window

Enables the Client to receive a Show in a Window rather than in full screen mode.

Scale to Fit

Automatically scales the Receive Show Window to resize the displayed screen in the available area.

Scrollbars

Determines if Scroll Bars will be displayed with the Receive Show Window for navigation.

Auto-Scroll Speed


When you are viewing a Show in a Window on the Client's screen, the Client can automatically scroll the contents when the mouse moves close to the edges of the window. Adjusting the sliding control sets the speed at which the view scrolls, from not at all to very fast.

Scroll Delay

When Auto Scroll is enabled, you can change the delay before the scroll is activated. If you want the view to scroll as soon as the mouse is at an edge of the screen, move the slider towards **Min**. If you prefer a longer delay before the AutoScroll takes effect, move the slider towards **Max**.

Audio Settings

This property sheet provides configuration options for using Audio Support at the Client.



Volume

Threshold – microphone sensitivity

Microphone – volume of microphone

Speaker – volume of speakers

Wave – volume of Operating Systems Sound Effects


Test

Check this box to test all of the above settings.

Client Interface Options

These property sheets are used for customising the interface between the Client and the Control.

Client Settings



Disable Client Menu items

Disable Request help

Prevents the Client User from being able to use the request Help Function.

Disable Call Control

Disables the Call Control facility on the Client Drop Down Menu.

Disable Disconnect

Prevents the Client user from being able to force the Control User to disconnect.

Disable Chat

Prevents the Client from initiating a Chat session with a Control. However, the Control can still open a Chat session with the Client.

Disable Replay

Prevents the Client from being able to open Replay Files.

Client Program Options

Icon in System Tray

The NetSupport Client icon will be displayed in the System tray rather than as a separate icon on the active application bar.

Always on Top

The NetSupport Client icon can become obscured behind other Windows. Setting this option means that it is always visible and the user at the Client will always know when someone is viewing them.

Hide when Idle

The NetSupport Client icon will not be displayed unless a Control is connected or viewing.

Quiet Mode (Client not visible on Taskbar)

Check this box to hide the Client icon on the Taskbar.

Silent Mode (no refresh)

Allows the Control to connect and View a Client without the Clients knowledge. If Silent Mode is not selected the Clients screen and mouse icon will flicker notifying the Client that a connection has been made and their screen is being Viewed.

Use internal speaker for Beep


By default, the audible warning beep, which can be sent between machines in functions such as Chat and View, comes from the PCs internal speaker. There may be occasions when it is more appropriate to use the workstations sound card to generate the beep through speakers, in which case un-check this box.

Beep while being Viewed (every n seconds)

While a Control is viewing the Client an audible beep will be sounded.

Help Request Settings

This property sheet is used for configuring the Clients Help Request access. You can specify the NetSupport Controls that the Client can forward Help Requests to or even link to a third party web based helpdesk system.



Select a URL for Help Request

If you use a 3rd party web based helpdesk application you can direct Clients to this rather than have them use NetSupports help request feature. To enable, check the Use URL box and enter the appropriate URL.

Available Controls

Lists the Controls that are available to connect to, from the Help Request and Call Control dialogs.

Options

Disable connections from Help Request dialog

Check this box to disallow the options in the Help Request dialog for the Client to choose which Control they wish to send a Help Request to.

Always show Controls in Help Request


Check this box to ensure that the Client Help Request dialog shows all Controls available for the Client to send their Help Request to.

Hotkeys for Request Help

This sets the hot keys that the User at the Client can press to raise an alert for Help. The alert will normally be displayed when a Control connects to the Client. If you are using a keyboard that won't support three scan codes, configure your Client to use only two hotkeys.

Customisable Text

This property sheet enables you to add customisable messages which are displayed at the Client machine.



Display Customisable Text

In About Box

Sets the message that will be displayed in the client's About Box.


When Connected

Sets the message that will be displayed at the Client when a Control Connects. Leave blank if you do not want any message displayed.

When Viewed

Sets the message that will be displayed at the Client when it is being viewed by a Control. Leave blank if you do not want any message displayed.

Profile Options



Disable this Profile when an NT user is logged on

If someone is logged in at the NT Client then this Profile will be deactivated and therefore not available to a Control user. The value of this is that it prevents a Control User inheriting rights on the workstation that they would not otherwise have.

Note: You can have two profiles with the same UserID but with different rights depending on whether the Client User is logged on at the time the Control connects. In this event make sure that the profile with this setting is the first in the list as it will then move on and use the second profile if the Client User is logged in.

User of this Profile has Priority over other (non-priority) Users

This works in conjunction with the option to allow more than one Control to connect simultaneously. If one profile has this set while the other does not the latter will be automatically disconnected.

Configuring the Control

In this chapter ...

How to configure the Control.

Create individual profiles ensuring each Control User can only perform certain tasks at Client PCs.

Configuring the Control

NetSupport allows you to fully configure how the Control Program will operate. To provide maximum flexibility NetSupport also allows you to set up multiple Profiles for different Control Users, each with their own access and functionality levels.

To access the Control Configurator

1. Choose {Network}{Configure} from the Control Window drop down menu for basic options (General, Connectivity, Security and Startup).
Or,
Click on the Settings icon for advanced Configuration options.
2. The Setting Configurations dialog for the current Profile will appear.

Note: If you want to change the Settings for a different Control profile you must use {Tools}{Configurations} and select the Profile you want to configure.

The Control Configuration options are categorised as follows:

General

This property sheet enables you to set the identification details for the Control.

Connectivity

These property sheets enable you to specify which transport protocols the Control will operate over.

Security

NetSupport Manager offers a wealth of security features that can be applied to each Control profile.

Startup

This property sheet enables you to configure the options that affect NetSupport Manager at startup.

Remote Control

These property sheets enable you to adjust the Remote Control features that apply to each Control Profile.

Control Interface

These property sheets enable you to configure the various components available to the Control from the Control Window interface.

File Transfer

These options configure the File Transfer Settings in NetSupport Manager. They allow you to alter the way in which information is displayed, and enables you to set safety features such as confirmation before performing a damaging operation.

File Locations

This property sheet allows you to specify where to store this Named Configurations Client, Group, Remote Networks, Tools and Scripting files.

Multiple Control Profiles


NetSupport allows you to set up multiple profiles for different Control Users, each with their own access and functionality levels.

Each configuration can be protected by a password and an icon can be created on the desktop to load the Control with a particular named configuration.

You must have NetSupport Administrator rights to profile or change a Controls Configurations.

To create a Profile

1. Choose {Tools}{Configurations} from the Control drop down menu bar.
2. The Control Configurations dialog will be displayed.



3. Select the Configuration that you want to change or choose New to create a new one. By default NetSupport is installed with a single profile called Standard. This is set up for full functionality.
4. Click Settings to tailor the global functionality of this profile.

Or,

Click on Connectivity and Startup Settings to tailor the Basic Functionality.

To create desktop icons

Having saved the profile, you can create a desktop icon containing the parameters required to load the configuration.

1. From the Configurations dialog, click Icons.
2. The Icon Maintenance dialog will be displayed.
3. Click anywhere in the dialog and drag to the desktop.
4. The Create or Edit Icon dialog will appear.
5. Enter the required configuration details and click OK to create the icon.

Adjusting Client Settings for a Control session

During any control session where you may be working with more than one Client, you can tailor how each Client interacts with the Control. For example, on one Client you may want to use compression because it is on a slow link, but on another you may want to turn compression off. NetSupport allows you do this by modifying the default settings for the current Control Profile.


To adjust View Settings

1. View the required Client.
2. Choose {View}{Settings for Client} from the View Window drop down menu.
Or,
Select the Settings button on the View Window Toolbar.
3. The Settings dialog will appear.
4. Configure which options will be enabled, when you start a View Session.

Note: If you edit the Client Settings, the changes you make only apply to that Client during the current Control session. If you want to change the settings permanently check the Update Configuration box.

General Settings

Use this property sheet to give the Control a specific name. If left blank, the machine name is used.



Identification

Control Name

The name which the NetSupport Control program uses when connecting to Clients to identify itself. Under NetBIOS this name is registered in the NetBIOS transport.

Description

Enter a description for this Control configuration.

Default User ID

If User Validation is required before a Client connection can be made, Control users will need to logon with a valid username and password. Rather than continually prompt for the username, a default ID can be set here. The following variables can be used in order to default to the currently connected username; %userdomain%\%username%.

Send Message


Title

Enables you to add a customised title to the Send Message dialog.

Connectivity Options

Before you can connect to Clients on your network you must select and configure the transports to use. The transport protocols must be configured in the operating system before attempting to use them.

Set TCP/IP Connection



TCP/IP

Use TCP/IP

Check this button to enable the Control to use the TCP/IP protocol. This protocol is used with the Internet, local and wide area networks. In order to connect to TCP/IP Clients you need to specify the port number that the Client is listening on.

Port

This value is used for all interactions with TCP/IP Clients. The default registered port for NetSupport is 5405. You can configure Clients on your network to run on a different port number if required. This is useful to provide additional security, as other NetSupport Control users would need to know on which port your Clients are configured. You can also specify a port number when creating or connecting to a client.

Note: To enable Clients to initiate a connection to the Control, the default registered port is 5421.

Connect By Hostname (DHCP/WINS)

Normally the Control connects to a Client by IP Address, rather than by name. In an environment that uses DHCP (Dynamic Host Configuration Protocol), this may be undesirable as the address may change when the Client workstation is restarted. Checking this option forces the Control to connect by hostname.

Test

Press this button to check the configuration and version of the TCP/IP stack installed. The version of Winsock is returned along with its current state.

Browsing**Subnets used when browsing for clients**

When you are running on a network with multiple subnets or addresses, you need to configure the Broadcast Addresses for each effective network. When a Browse is performed, the broadcast messages are sent to these addresses.

Broadcast Show

When showing the Control screen to clients, the screen information is sent to each client machine in turn. Enabling Broadcast Show results in the screen information being sent to all machines simultaneously. In some network environments where there is limited network bandwidth available or when showing to larger numbers of machines this will provide significant performance benefits.


Whilst reducing overall network traffic generated by NetSupport, using this feature will generate additional broadcast packets on your network. It is recommended that you consult your Network administrator before using this feature.

Note: If you encounter problems broadcasting to Clients, you may need to upgrade the version of the NetSupport Client that is installed on the target machines. The broadcast show feature is only supported in version 7.10 or higher.

Settings

If Broadcast Show is enabled, select this option to set the Broadcast Address. The Broadcast Settings dialog will appear.

Set IPX Connection



IPX

Use IPX

Check this box to enable the IPX transport protocol. This protocol is used on local and wide area networks.

Record Clients' Network Numbers

When IPX addresses are recorded for a client, the network number is normally set to 0 if the Clients are on the same IPX network as the Control (this prevents subsequent problems when a file server is down). This setting forces network numbers to be recorded and used when establishing a connection.

Use Networks

The Control normally obtains a list of network numbers from the nearest NetWare server or bridge. On some networks, there is no NetWare server to ask or the list generated is unreliable. Enter one or more network numbers to use, which replaces the normal discovery mechanism. The numbers can be in decimal or hexadecimal, and must be separated by commas. Such as "0x1, 0x2, 0x34db1d69". You can also use the **Test** function to determine these values automatically.


Ignore Networks

This list of network numbers is generated in the same way as for **Use Networks** except that when browsing, these network numbers are ignored. You can also use the **Test** function to determine these values automatically.

Test

Press this button to check the IPX network configuration. This determines if the IPX network stack is available and configured correctly. You can also scan the network for network numbers that do and do not respond.

Set NetBIOS Connection



NetBIOS

Use NetBIOS

Check this box to enable the use of the NetBIOS transport. NetBIOS is a non-routed protocol and is only used on Local Area networks (LAN). Using NetBIOS requires that you select one or more adapters to use. See adapters below.

Adapters


This list box contains the NetBIOS adapters that have been detected in your workstation. Select one or more of these adapters for use in the control. NetBEUI is the most common adapter used here, as it is used primarily by Windows systems. The adapter numbers will vary from workstation to workstation, but the names will remain constant.

Test

Press this button to test the NetBIOS stack and determine the adapters available. You can also display detailed information about each adapter found.

Set HTTP Connection

This property sheet enables you to configure the Control to communicate via HTTP. For more information see, [Connecting Clients/Controls via a NetSupport Gateway](#).



Use HTTP:

Check this box to enable the Client to communicate over HTTP.


Port:

NetSupport's default port for HTTP communications is 443.

Note: In version 9.10, Port 443 was introduced as the default for HTTP communications, 3085 being used previously. Gateway settings will be preserved for existing customers who subsequently upgrade, enabling 3085 to continue to be used, but there may be scenarios when upgraded Controls and Clients will need the HTTP Port manually reconfiguring to ensure compatibility.

Remote Dialup Settings

This property sheet provides configuration options for the Dial-up Settings for Remote Networking. Before you can dial remote networks, you must enter information about your modem hardware. To dial a Bridge at startup, select Configure from the Networks drop down menu and click on the Startup option.



Modem

NetSupport displays all available modems here. Simply select which Modem you wish to use.

Dual Channel Bonding

If enabled, both channels of your ISDN line are combined thus increasing the amount of available bandwidth to 128k. However, in increasing the speed of transmission you are in effect making two calls.

MSN (Multiple Subscriber Number)

Specify a number that you want the Control to answer an incoming dial-back from a Client Bridge.

Diagnostics

None

Select this option to perform no diagnostics on your modem.

Basic

When the modems connect, the Control checks the following:

Flow control is correctly set (XON/OFF is disabled, etc)

There is a NetSupport Bridge at the remote number

There are not excessive delays in transferring data

Extended

The Extended setting performs the same checks as for Basic and includes:

Line reliability

Throughput

Logging Level

None

Select this option to display the progress messages on the screen only.

Basic

Selecting Basic logs the following information to MODEM.LOG:

The name of the modem used

The number dialled

Results of Diagnostic tests

Connection speed

Verbose

Selecting Verbose records the same information as Basic, but includes timestamps.


Use this option if you are having problems establishing dial-up links.

View Log

Opens a window that displays the MODEM.LOG file generated by

Extended and **Verbose** Diagnostic and Logging settings.

Advanced Settings



Tickle Period

Specify the period in seconds between tickle packets that are sent to the client. These packets check to make sure that a connected Client is still active. If the Client fails to respond, the Control assumes that it is no longer present and will close down the connection.

Name Lookup Delay

Specify the delay in seconds between broadcast packets. Use this value in conjunction with **Name Lookup Attempts** to reduce the amount of time spent performing browses. The browse is more likely to miss Clients if this value is too small. You should not specify a value that when multiplied by the **Name Lookup Attempts** value is less than 4 seconds.

Name Lookup Attempts


Specify the number of name lookup packets the Control broadcasts during a Browse. The fewer broadcasts that are sent the lower the network traffic and the quicker the browse will complete.

Security Options

The Control Configurator provides a wealth of security features categorised as follows:

- Settings
- Event Logging
- Replay Files
- User Permissions

Security Settings



Password

Enter the Security Password, which you will be prompted for when starting the Control using this configuration. You must click on the **Set** button next to this Control to set the password.

Security Key

The Security Key is used whenever you connect to a Client. Unless the key entered here matches the security key on the Client, you will be denied access to the Client workstation. Press the **Set** button to change the key. Optionally this can be set as the serial number in your NetSupport Licence File.

Prompt for Additional Information when connecting

If this box is checked, you will be required to supply a reason for connecting to a Client workstation. This is sent to and displayed at the Client so that the user knows why you are connecting when the Client has User Acknowledgement enabled.

Try Last Username before displaying login Prompt

Remembers the username and password attached to a named configuration and will attempt to login using this information.

Use Compression


Check this box to enable the use of compression. When you are communicating with a Client, whether it is a File Transfer, View or chat session the data being sent and reviewed will be compressed. This also provides a means of security, as the data will also be encrypted.

Use Encryption

With encryption turned on, all the information that is sent between the Control and Client is very difficult for others to read. NetSupport offers a range of encryption options, ranging from 56 Bit DES to 256 Bit AES, enabling you to find the necessary balance between security and performance. The higher the level of encryption, the higher the potential for decreased performance.

Event Logging

This property sheet enables a NetSupport Control to record, in a text file, the actions it has performed while remote controlling a Client. This may be useful for maintaining a history of how often a particular Client was connected to and for what purpose.



Enable Logging

Check this box to enable the 'Log to File' option. Once enabled, each time the Control subsequently connects to a Client(s), the activity for that session will be recorded.

Log to File

Specify the path and file name for the Log File. The NetSupport default is PCICTL.log. This file can be stored on the Local workstation or on a Server. Multiple Controls can write to the same Log file.

As User (NT/2000/XP Only)


Log File User is the user name and password used to be able to write to the log file when the path specified is a UNC Path.

Append to Logfile

By checking this box, NetSupport will continually add to the existing entries in the log file. If unchecked, existing items get overwritten.

Replay Files

The Replay Files feature enables the Control to record and playback the screen activity that takes place at a Client workstation while it is being remote controlled/viewed.



Record Replay Files

Check this option to enable the recording of Replay Files. A Replay File will be created each time the Control views a Client PC.

Include Audio

In addition to recording the screen, mouse and keyboard activity, if Client machines are configured for audio you can include any narration that takes place.

Prefix Files With Client Name


In order to identify each Replay File, filenames are prefixed with the Client Name and the date/time of the recording. Alternatively, by unchecking this box the files will be named sequentially in the format 00000001.rpf etc.

In Directory

Specify where the Replay Files should be stored.

User Permissions

These settings restrict the items that a user running a configuration can modify. Only if this configuration is running as an NSM Administrator can you restrict the privileges of other users.



Permit a user of this Configuration to

Act as an Administrator

When this box is checked there are no restrictions applied to the user of this configuration. This should be enabled for at least one account, to allow you to alter other configurations.

Change Settings


This box is only available when the configuration is not running as an Administrator. Check this box to prevent the user running this configuration from changing any settings from within the user interface.

Configure User Interface

This check box is only available when the configuration is not running as an Administrator, and Change Settings is checked. Check this box to prevent the user of the configuration from altering any settings that affect the User Interface.

Startup Settings

This section configures the options that affect NetSupport Manager at startup. You can connect to a Client, Group or Remote Network or even perform a Browse. This enables you to perform a repetitive task that you would normally do every time you start the Control.



At Startup

Dial Remote Network

Check this box if you want to dial a Remote Network when the Control starts. When this item is checked the list of remote networks configured is enabled. Select one of these networks to continue.

Connect to Client

Check this box to connect to a Client when the Control starts. All of the clients in your Known Clients List will be displayed here, with the transport appended to the name. For example, TEST1<TCP>.

Connect to Group

Check this box to connect to a group of Clients when the Control starts. All of the groups created will be displayed in this list.

Browse for Clients starting with ...

When the Control starts it can perform a Browse using the information supplied. Enter a partial Client name or leave this blank to find all available Clients. The Clients found will appear in your Browse folder in the Tree View.

Start Viewing

When you have checked one of the Connect boxes above, you have the option to view the Client when the control starts. Check this box to enable the three buttons below. This allows you to choose the way in which the Client is viewed.

Watch

Start Watching the Client or Clients when the Control starts.

Share

Start Sharing the Client or Clients when the Control starts.

Control

Start Controlling the Client or Clients when the Control starts.

Icons

This utility allows you to create icons on your desktop that load a NetSupport Control with a specific Named Configuration. This means that you can have several shortcuts that automatically connect to one or more Clients when run.

Disconnect

The following options are only available on non-Administrative configurations.

Exit Program on Disconnect

Check this box to force the Control to shutdown when you disconnect from a client. This option is very useful when used in conjunction with the option above and connecting to a Client at startup.

Exit Program after Hanging up the phone

Check this box to force the Control to shutdown once a dial-up session has been completed. This is most useful when used with dialling a Remote Network at startup.

Remote Control Settings

The following property sheets enable you to configure the behaviour of the remote control options when viewing Client workstations.

View


Keyboard/Mouse

Print Capture

Audio

View Settings

This property sheet provides configuration options for Viewing Client workstations. If editing the Client Settings, all changes you make will only apply while you are connected to that Client. If you wish to make your changes the Control default, check the Update Configuration box.



Options

BIOS Keyboard

Checking this option causes the Control to emulate keystrokes on the Client at the BIOS level, rather than the Hardware level. Use this if an application at the Client does not appear to be correctly accepting keystrokes from the Control. Only use this option if you are experiencing problems with the default low-level keyboard option.

Confirm Switch to Full Screen

When this box is checked, you will be prompted to confirm switching to Full Screen Mode.

Full Screen

Checking this options will force the Control to view a Client in Full Screen Mode rather than in a windowed mode.

Scale to Fit

Check this option if you want the contents of the View Window to be automatically shrunk to fit the sizeable frame.

Disconnect when Closed

Check this option to disconnect from a Client, when a View Window is closed.

Screen Scrape

NetSupport's favoured, and the most efficient, method for capturing screen data is to hook into the Video Driver of the workstation being viewed. However, there may be occasions when this method will not work because certain applications bypass the driver. In these circumstances you can enable 'screen scrape' mode in order to take a snapshot of the screen. Although this will have a greater impact on the network it will at least provide an accurate representation of the Client's screen.

Scrollbars

You can turn off scrollbars on the View Windows by un-checking this option. This is useful when using Auto-Scroll, as you gain a little extra workspace.

Use Compression

Check this box to enable compression when viewing a Client's screen. The state of this checkbox is also reflected in the General Settings.

Wallpaper

Check this box if you want the Client's wallpaper to be visible when viewing. Normally this is turned off to improve performance, so expect the screen update speed to be impacted by selecting this option.

Blank Client Screen

This enables the Control operator to blank the Client screen in any of the View modes.

Note: If another Control, with the Blank Client Screen setting checked, attempts to connect to a Client being controlled in Blank Client Screen mode, the original Control will be disconnected. This is to prevent less privileged users from 'surfing in' on the back of a more privileged user.

Video Skipping

NetSupport Controls can now be configured for Viewing performance. The Control program will not display Client screen updates if a subsequent update to the area of the screen is made. Un-ticking the box will result in all Client screen updates being displayed at the Control.

Default Mode

When you view a client, by default, you start viewing in Share Mode. If you prefer to start viewing in a different way, change the style from the list provided.

Cache Size

The NetSupport Control contains a cache to help improve overall performance. The cache sizes range from 256k to 16Mb and a separate cache is allocated to each Client connection. If you are running applications on the Client that uses lots of or large bitmaps increase the cache size to improve the performance.

Max Colour Depth

When you connect to a Client, you can restrict the Colour Depth that is sent. This is done to reduce the amount of traffic between Client and Control. Reduce the Colour Depth to **16 colours** if you are using applications that do not rely on anything other than the standard 16-colour palette.

Note: The colour depth set here will be overridden by the settings in the Clients Configuration, preventing you from setting the colour depth at a higher level. To alter these settings at the Client, load the Advanced Configurator and select **Remote Control - View** and amend the **Max Colour Depth** to the required level.

Change DOS Font

Use this dialog to select the font to use when displaying DOS screens. This will be either from DOS Clients or Windows Clients running Full Screen DOS boxes. Windows uses a graphic character set for displaying DOS Screens. The higher the resolution that you are running Windows in the larger the font size you will need to set to get an accurate representation of a DOS Screen.


Change Japanese Font

Use this dialog to select the font to use when displaying Japanese DOS screens.

Update Configuration Standard

Check this box to update the currently selected Configuration.

Keyboard/Mouse Settings



Keyboard Layout

Select from the list provided a keyboard layout to be used at the Control during viewing. These layouts map keys on the Control to keys on the Client workstation. If both Client and Control are using the same keyboard layout, you should select **Unmapped Keyboard** from the list.

Hotkeys

When you are Viewing a Client in Full Screen Mode, hot keys provide a way of returning to the, possibly hidden, user interface. If the screen resolution at the Client is smaller than the resolution of the Control, you can simply click your mouse button outside the View Window to stop Viewing and display the View Window again. Check the boxes in this group to determine the keys that are used as Hotkeys.

If you are using a keyboard that does not support three scan codes, choose only two options as your hot keys.

AutoScroll Speed

When you are viewing a Client's screen, the Control can automatically scroll the contents when the mouse moves close to the edges of the window. Adjusting the sliding control sets the speed at which the view scrolls, from not at all to very fast.

Scroll Delay

When Auto Scroll is enabled, you can change the delay before the scroll is activated. If you want the view to scroll as soon as the mouse is at an edge of the screen, move the slider towards **Min**. If you prefer a longer delay before the AutoScroll takes effect, move the slider towards **Max**.

Mouse Delay

Adjusting the mouse delay allows you to reduce the rate at which mouse updates are sent from the Control to the Client when controlling or sharing. Move the slider control towards **Infinite** to reduce the rate and conserve bandwidth, or towards **Min** for the best mouse response. This is useful on dial-up or very slow networks.

Disable Num Lock Synchronisation


Check this option if using a Laptop as the Control machine to ensure that the keyboards behaviour corresponds with that of a standard desktop machine.

Update Configuration Standard

Check this box to update the currently selected Configuration.

Print Capture Settings

Print Capture redirects printer output from a local printer at the Client, to the printer or file at this Control. You would use this when running an application on a Client but want any printed output redirected to the printer that is local to you.



Enable Print Capture

Check this box to enable the Print Capture feature. If this box is unchecked, the output will be printed at the Client.

Notes:

- This option can also be enabled whilst viewing a Client left click Print Capture at the bottom of the View Window and select **Enable**. Alternatively select **Options** to configure all Print settings.
 - In addition to enabling this option at the Control you also need to ensure that Print Capture is enabled in the Clients Configuration. The privileges are enabled by default.
-

These options specify where the printed output will be redirected to on the Control. This can be either a local or network printer, or a file.

Capture to Printer

Select this radio button to redirect the Client printing to a local or network printer. The name of the default printer that is currently set-up is displayed.

Change

Press this button to display a window containing all of the printers configured on your local workstation.

Capture to File

By selecting this button, you can redirect the Client printing to a file that can be printed later. This file can be on a local or network path.

Browse

A file browse window will appear when you press this button allowing you to find a location for the capture file.

Use Client Printer Driver

NT Clients try to use the correct driver for the Control's default printer (by changing the default printer on the Client workstation, although not all applications notice this). For this to work, you need to install the appropriate printer driver on the Client and assign it to LPT1, LPT2 or LPT3.

On Windows 95 and Windows NT, the user can change the printer name (in **Control Panel, Printers** or **Settings, Printers**). To handle this situation, and because printer and driver names vary between, Windows 95 and NT, you can specify a list of printer names and Drivers in this field. For example:

HP DeskJet 520,DESKJETC; HP DeskJet...

Where:

HP DeskJet 520 is a printer name that the Client might recognise
DESKJETC is the name of the driver file for this printer at the Client (optional, .DRV assumed)

HP DeskJet is another printer name that the Client might recognise

When Print Capture is enabled, the Control sends this information to the Client, and the Client then looks for the closest match in the Drivers installed on the Client workstation. The NT Client ignores the name of the driver file; the Clients match this preferentially, using the printer name only in case of a tie.

Report Driver Used

When you connect to a client a dialog box will appear informing you of the printer driver that has been used. If no matching Drivers were found you would be informed whether you check this box or not.

Notes

- Print output is captured only from the port to which the default printer is attached. Note that the Client may change this when Print Capture is enabled, as described above.
 - The Windows NT Client captures print output from DOS programs from the port to which the default printer is attached.
-

If you experience problems with the Windows Client, try:

- Disable 'fast printing direct to port' at the Client
- Removing any connection to a network printer at the Client.
- Change the printing priority at the Client to **Low** in **Print Manager, Options, Background printing**.
- To capture printed output from DOS programs running under Windows 95, open **Printers, Settings**, <Your printer>, **Properties, Details, Port Settings** and ensure that **Spool MS-DOS print jobs** is *not* checked.

Update Configuration Standard


Check this box to update the currently selected Configuration.

Note: If you are editing the Client Settings, any changes you make to this property sheet will only apply while you are connected to that Client. If you wish to make your changes the Control default, check the Update Configuration box.

Audio Settings

This property sheet provides configuration options for using Audio Support.

If you are editing the Client Settings, all changes you make will only apply while you are connected to that Client. If you wish to make your changes the Control default, check the Update Configuration box.



Volume

Threshold – microphone sensitivity

Microphone – volume of microphone

Speaker – volume of speakers

Wave – volume of Operating Systems Sound Effects

Test – Click on Test, to test the volume settings as you adjust.

Enable

On – turn Audio on

Off – turn Audio off

Talk – turn the Control Audio to Talk function only

Listen – turn the Control Audio to Listen function only


Selecting the Audio Transmission Format buttons allows you to change the Transmission Format. Use only the level you need for acceptable quality. High quality settings can affect screen update performance. Over Remote Communication links we recommend you use a Transmission Format of less than 2 kb/sec.

Control Interface Settings

These property sheets enable you to configure the different components available to the named configuration.

Interface Settings

This property sheet enables you to configure the different components available to the named configuration.



Settings

Hide Client List

Check this option to disable the display of known Clients for security reasons. The Clients branch is removed from the Tree View and all of the menu and toolbar items that allow you to manipulate Client records are removed.

Hide Group List

Check this box to disable all the display of Groups for security reasons. The **Groups** branch is removed from the Tree View, and all related menu items and Toolbar buttons are removed.

Hide Dial Directory

Check this box to disable all Remote Network functions. The **Remote Networks** branch is removed from the Tree View, and all related menu items and Toolbar buttons are removed.

Hide Gateway

Check this box to disable the Gateway function. The **Gateway** branch is removed from the Tree View.

Disable Browse

Check this box to disable the Browse function. The **Browse** branch is removed from the Tree View, the Toolbar button is removed and the related menu item is removed.

Use internal speaker for Beep

By default, the audible warning beep, which can be sent between machines in functions such as Chat and View, comes from the PCs internal speaker. There may be occasions when it is more appropriate to use the workstations sound card to generate the beep through speakers, in which case un-check this box.

Client List Read-only

Check this box to remove the ability to alter the Known Client List. The **Clients** item is still available in the Tree View, but you cannot modify or create new Clients.

Group List Read-only

Check this box to remove the ability to alter the Groups list. The **Groups** item is still available in the Tree View, but you cannot modify or create new groups.

Dial Directory Read-only

Check this box to remove the ability to alter the Remote Networks list. The **Remote Networks** item is still available in the Tree View, but you cannot modify or create new items.

Gateway Read-only

Check this box to remove the ability to alter the Gateway list. The **Gateway** item is still available in the Tree View, but you cannot modify or create new items.

Message on Disconnect

When checked, the Control user will be prompted to send a message to the Client when disconnecting. This may be useful to notify the user on the Client workstation that the Control user has finished using the workstation and advise what action has been taken.

Silent Disconnect

Should a Client inadvertently disconnect during a session, a prompt appears at the Control machine. Check this option to disable the warning.

Shell Extension


NetSupport Manager integrates directly with Windows Explorer allowing you to launch key functionality direct from your system without needing to first start NetSupport.

Disable Shell Extension

Check this box to remove NetSupport functionality from the Explorer shell.

Functions

This property sheet enables you to restrict the functionality that is available to the Control.



Restrict Functionality

You can prevent the following features from appearing in the Control profile by checking the appropriate boxes:

- Disable File Transfer
- Disable Chat
- Disable Send Message
- Disable Broadcast Message
- Disable File Manager
- Disable Duplicate Client Check*
- Disable Quick Connect
- Disable Remote Command Prompt
- Disable Reboot
- Disable Logoff
- Disable Replay
- Disable Execute
- Disable Registry Editing (This option is disabled by default)
- Disable Blank Screen
- Disable Inventory

- * When browsing for Clients, NetSupport checks for duplicate Client details, only connecting to the first occurrence of a particular address. Depending on the setup of your network infrastructure there may be instances where duplicate IDs are in use, so you can disable the check using this option.


Remote Control

The following items disable the different view functions within the NetSupport Manager Control.

- Disable Control
- Disable Share
- Disable Watch
- Disable Show

Help Request Settings

This property sheet provides configuration options for receiving Help Requests from Clients.



When a Help Request Arrives:

Highlight the Client in the Help Request List

Check this box to highlight the Client icon in the List View when a Help Request is sent.

Display a Message

Check this box to have Help Request messages displayed on the Control screen.

Play a Sound

Check this box to play a sound when a Client sends a Help Request. Use the Browse function to specify the sound.

Control Status (for incoming Client Connections)

Available to take Help Requests

Check this box to be available to receive all incoming Help messages.

Not Available to take Help Requests

Check this box and not receive any Help messages.

Busy at the moment

Check this box to be available to receive all incoming Help messages, but not when connected to xxx number of Clients. Ensure that you specify the number of Clients you need to be connected to, in order to be considered busy.


Set Status to 'Busy' when connected to xxx or more than, Clients

Ensure that you specify the number of Clients you need to be connected to, in order to be considered busy.

File Transfer Settings

This property sheet provides configuration options for transferring files. They allow you to alter the way in which information is displayed, and enables you to set safety features such as confirmation before performing a damaging operation.

If you are editing the Client settings, all changes you make will only apply while you are connected to that Client. If you wish to make your changes the Control default, check the Update Configuration box.



Display Options

Show System/Hidden files

Check this box to display all files with System and Hidden attributes. By default, this option is unchecked.

Show file details

Select this option to display multiple columns of information for each file in the list. These show the file size, modified date, attributes and short filename. You can toggle between this state and the filenames only state, by using the list style buttons in the File Transfer User Interface.

Show file names only

Select this option to only display filenames in the file lists. This allows you to display more files at the same time than with file details. You can toggle between this state and the Details State, by using the list style buttons in the File Transfer User Interface.

Confirm

When you perform potentially dangerous file operations, such as deleting a directory or file you can make the Control display a Confirmation dialog box. This helps prevent accidental loss of data. If you are familiar with the User Interface, you can turn these options off as required. By default, all the confirmation settings are turned on.

Directory copy

Make the user confirm before copying a directory structure.

Directory delete

Make the user confirm before deleting a directory structure.

File overwrite

If checked, displays a confirmation dialog before overwriting an existing file. However, if unchecked the confirmation message will still appear if system/hidden files are about to be overwritten.

File delete

Display a confirmation dialog before deleting one or more files.

Use Compression

Check this box to enable the use of compression. When you are communicating with a Client, whether it is a File transfer, View or Chat session, the data being sent and received will be compressed. This also provides a means of security, as the data will also be encrypted.

Delta File Transfer

Delta File Transfer improves performance by skipping the transfer of information that is unchanged. If the file being transferred already exists in the destination directory only the changed parts of the file will be updated.

Delta File Transfer is enabled by default.

Priority (when also Viewing)

When you are transferring files and viewing a Clients' screen at the same time, each operation impacts the performance of the other. You can reduce the priority of a file transfer operation to make the viewing more responsive and vice-versa. Slide the control to the left to give the file transfer higher priority, or to the right to give Client views higher priority. If you are not viewing a Client, this setting is ignored.


Update Configuration Standard

Check this box to update the currently selected Configuration.

File Location Settings

This property sheet provides configuration options for Client, Group, Remote Networks, Tools and Scripting File Locations. This facility allows a Control user to have unique Control files, enabling a Control user to access their Control files from any Control workstation.

If you are editing the Client Settings, all changes you make will only apply while you are connected to that Client. If you want your changes to become the Control default, check the Update Configuration box.



Client File

Use Browse to specify an alternative location for all Control's, Client details. To make files Read Only, check the Client List Read Only check box, in the Control Configuration User Interface settings.

Group File

Use Browse to specify an alternative location for all profiled Control's, Group details. To make files Read Only, check the Group List Read Only check box, in the Control Configuration User Interface settings.

Remote Networks File

Use Browse to specify an alternative location for all profiled Control's, Remote Network details. To make files Read Only, check the Dial Directory Read Only check box, in the Control Configuration User Interface settings.

Tools File

Use Browse to specify an alternative location for all profiled Control's, Tool details. There is no facility to make these files Read Only.

Scripts File


Use Browse to specify an alternative location for all profiled Control's, Script details.

NetSupport Protect – Switch Desktop Protection Off

NetSupports desktop security product, NetSupport Protect, compliments NetSupport Manager range of functionality by further protecting Windows® operating systems and desktops from unwanted or malicious changes.

If NetSupport Protect is installed on the Client machine you may need to disable the protection in order to conduct your remote control session.

To Disable NetSupport Protect choose **{View}{Settings for Current Configuration – NetSupport Protect}** from the Control Window drop down menu.



Disable NetSupport Protect

Decide whether to switch protection off when you first connect to the Student machines or when you open a view session.

Security

A NetSupport Protect configuration should be secured with an Administrator password. You will need to enter that password here as confirmation that you are authorised to turn desktop protection off.

To find out more about NetSupport Protect and to download a free trial copy, visit **www.netsupportprotect.com**.

Managing and Organising Clients

In this chapter ...

You will find out how to better manage your database of Client PCs. Group Clients by department or geographic location and customise the properties of each Client.

Add a new Client

NetSupport Manager maintains a database of all Known Clients. These are stored in the Clients Folder in the Tree View and provide a fast way to connect to those Clients without having to perform a Browse.

You can also see additional information about the Client such as names, contact numbers etc.

To populate the Known Clients database, do one of the following

1. Use the Browse function to lookup available Clients and connect to them. All required information about that Client will then be stored in the All Computers folder.

Or,

Choose {Client}{New} from the Control Window drop down menu and manually enter the details.

2. You will then be prompted for the following information:

- The name of the Client;
- The Network Transport it is running under;
- The Network address of the Client.

At this point, you can choose to enter some additional information to be stored with that Client's details. The information you can additionally store is:

- An alternative name to be displayed at the Control for that Client;
- A text description about that Client;
- A Contact Name;
- A Contact telephone Number.

The newly created Client will now appear in the All Computers Folder and be displayed in the Clients List View.

Delete a Client

As part of maintaining a database of Known Clients, good house keeping requires deleting unused previously saved Clients from the Clients Folder in the Control Tree View.

To delete a Known Client from the database

1. Open the All Computers Folder in the Tree View and select the required Client.
2. Right click on the Client and choose Delete.
Or,
Choose {Client}{Delete} from the Control drop down menu bar.
3. The 'Delete a Client' dialog will appear and prompt for confirmation.

Renaming a Client

Instead of displaying the Clients physical name, NetSupport allows you to set a different name that will be displayed at the Control.

For example, a workstation running a Client may have a description allocated by you such as Sales 2. This workstation may move to the Accounts department and as such you wish to rename it as Accounts 3.

To Rename a Client

1. Open the All Computers folder in the Tree View and select the required Client.
2. Choose {Client}{Rename} from the Control Window drop down menu bar.
Or,
Right click on the Client and choose Rename.
Or,
Right click on the Client icon and choose {Properties}{Details}.

Note: This only changes the stored name on the Control. It does not affect the physical name of the Client that will be displayed at another Control or if you do a Browse.

The Details Tab

Details about the person responsible for the Client workstation and descriptions are displayed here. All of these fields are optional.

Display Name

Use the Display Name to provide a friendlier name for the Client to be displayed at the Control. By default, the physical Client name is used.

Description

Enter a description for the Client, or some notes that may help in the future.

Contact

This is the name of the person responsible for the maintenance of the Client workstation. This is particularly useful on WAN's where one person may not be responsible for all Clients.

Phone Number

This is the contact telephone number for the person responsible for the Client workstation, as supplied above.

Setting Client Properties

You can store additional information about a Client workstation and its User by completing the Properties sheet for the Client. This information can then be viewed in the Detailed List View. You choose which fields are displayed by using the {View}{Columns} function from the Control Window drop down menu bar.

To Adjust Client Properties

1. Open the All Computers Folder in the Tree View and select the required Client.
2. Right click on the Client and choose {Properties}.
Or,
Choose {Client}{Properties} from the Control Window drop down menu bar.
3. The Clients property sheet will be displayed.

The Client property sheet has three tabs: General, Details and System Info. The System Info is only displayed once you have connected to the Client.

The General Tab displays the following information:

- The Physical Client name;
- Its Network Address;
- The transport it is using;
- Whether you wish to include the Client in Shows/Scans.

The Details Tab displays the following information:

- The name you want displayed at the Control for this Client;
- The Description that you want to associate with this Client;
- The Contact name;
- The Telephone Number;
- The Mac/Ethernet Address.

The System Info Tab displays the following information:

- What version of NetSupport Manager the Client is running;
- What operating System it is running on;

Creating a New Group

NetSupport allows you to organise Clients into Groups for easier access and management. For example, you might group all the Clients in the Accounts department in to a single group called Accounts. You can also create Sub Groups which are attached to a group, this maybe useful if the Accounts department has different offices, you can then have a sub group for the London Office and one for the Cambridge Office.

To Create a Group

1. Make sure that the required Clients have previously been connected as this will store them in the Known Clients folder and make them available for grouping.
2. From the Control Window drop down menu choose {Group}{New}.
or,
Click the New icon on the Control toolbar and choose Group.
3. This will display the Create New Group Wizard that will guide you through the process of adding or removing Clients in your new Group.

To Create a Sub Group

1. Make sure that the required Clients have previously been connected as this will store them in the Known Clients folder and make them available for grouping.
2. Select the Group that you wish to attach the sub group to.
3. From the Control Window menu bar, choose {Group}{New}.
or,
Click the New icon on the Control toolbar and choose Group.
4. This will display the Create New Group Wizard. This will guide you through the process of adding or removing Clients in your new Group.

Note: Clients specified in a sub group will also appear in the Group above it.

Adding/Removing Clients in a Group

NetSupport allows you to Group Clients together to allow easier management.

For example, you may have a number of workstations all associated with the Sales department. By placing each of the individual Clients in a predefined group, you can then perform operations in a single action to all members within that group.

To Add Clients to a Group

1. Select the Client in the List View.
2. Choose {Client}{Add to Group} from the Control Window drop down menu.
3. Select the Group you want to add the Client to, click Add.

Or,

1. Open the All Computers Folder, highlight the group you want to add the Client to and right click.
2. Choose {Properties- Members Tab}.
3. Select which Client you wish to add to the Group, click Add.

Or,

1. Select the Client in the List View.
2. Right Click and drag & drop the Client into the relevant Group.

To Remove Clients from a Group

1. Open the All Computers Folder, highlight the Group you want to remove Clients from and right click.
Or,
Choose {Group}{Properties- Members Tab} from the Control Window drop down menu.
2. Select the Client(s) you wish to remove from the Group and click Remove.
3. When you have finished adjusting the members of your Group, click OK.

Note: To move a Client to a different Group, right click the Client icon and drag & drop to the new group. This will remove the Client from all levels in the previous group.

Setting Group Properties

Having created a Group you may be required to review or change its name, description or members.

To adjust a Groups Properties

1. Highlight the required Group from the Tree View.
2. Right click on the Group and choose Properties.
Or,
Choose {Group}{Properties} from the Control Window drop down menu bar.
3. The Group Property sheet will be displayed.

The Group Property Sheet has two tabs:

General

Shows the name and a description of the group, you can also customise the appearance of the client icons.

Members

Lists the Clients in the Group.

Remote Communications

In this chapter ...

Learn how to use NetSupport Manager's comms options, enabling you to reach the remotest of Clients.

Remote Communications Overview

NetSupport Manager supports communications over modems, the Internet, ISDN or direct serial links on all protocols and operating systems. You can either use NetSupport's own Remote Communications programs or a third party remote access product such as Microsoft's Remote Access Server.

Accessing remote workstations for remote control, has never been easier.

If you are using NetSupport's own Remote Communications programs to dial-in to a Client workstation or network, you must install the NetSupport Bridge on the Client workstation or a workstation on that network, and the NetSupport Remote option on the workstation that is to be used as the Control to dial-out.

The Bridge and Remote modules provide an interface that allows the Control to connect to remote Clients, as if it were on the same LAN. However, neither the Control nor the Client workstation needs to be physically attached to a LAN.

Optimising Remote Connections

Performance is naturally affected when communicating with a Client over a dialup link. To get the most out of your remote connections follow these simple steps.

- Use the highest speed modems you can.
- Set the Mouse Delay to the highest possible level.
- Ensure the modems are configured correctly, use the modem diagnostics and logging to check the throughput.
- Use a large cache at the Client and Control. Specifying a large cache means the Control can store more areas of the screen locally without having to ask the Client to send them again.
- Make sure NetSupport's compression is turned on and the modem's compression is disabled in Windows TAPI Setting.
- Limit the colour depth to 16 colours. This means that all images sent from the Client to the Control are 16 colour only. A high colour bitmap can be 2 or 3 times the size of a 16-colour bitmap. This will improve performance with the only side affect being that images won't look as good.
- Run the Client in a reasonably low resolution. The lower the resolution the less information the Client needs to send. If you can work at 640x480 or 800x600 then set the Client to this. The Control doesn't have to be at the same resolution as the Client.

Setting up Remote Communications

The sequence of events for establishing a remote communications link is:

At the (Client) Remote End

1. Turn on the modem.
2. Load the Client Bridge. This process can be automated so that the Bridge is automatically loaded when NetSupport is initialised. See 'Client Configuration Dialin Bridge Settings'.

At the Control

1. Turn on the modem.
2. Start NetSupport Control program and choose {Network}{Remote}{Dial - New}.
3. The Add a remote Network dialog will be displayed. This dialog prompts you through the process of creating a remote Network profile.

You must enter the following information:

- The Name that the connection will be known as.
- The Telephone Number of the NetSupport Bridge to Dial.
- The Transport, IPX, NetBIOS or TCP/IP to be used.

Once a dial-up or serial link has been established, operation is the same as on a LAN.

If you are using RAS or another third party remote Access product then simply make the dial-up networking connection before starting the Control and use the Control as if it were on the Local LAN.

Note: In order for the connection to work, you must ensure that the corresponding NetSupport Bridge has been set up on the Remote Network or Standalone workstation.

The NetSupport Bridge

When loaded on a networked workstation, the NetSupport Bridge provides access to all other Clients, whatever their operating system, on the same network.

Likewise all NetSupport Controls, whatever the operating system, can dial into all versions of the Bridge program.

To load a Bridge

The NetSupport Bridge is loaded with a standard Client to provide access to all workstations on the network. You use the NetSupport Configurator to set up the bridge:

1. Start the NetSupport Client Configurator on the workstation that will be used as the Bridge.
2. Choose {Connectivity - Dial-in Bridge}.
3. Follow the instructions in Configuring a NetSupport Bridge.

Effect

A Control can dial-in and take control of any Clients on that remote network which are running on the same protocol as the Bridge. It is possible to have the Bridge running on one protocol and the Client on another, however, in this case the Control will not be able to access the Client as the Bridge.

Use this option if

You wish to provide dial in access to this workstation or a NetSupport Client on the same Network.

Note: To configure the Control Bridge choose {Network}{Configure}{Connectivity – Remote Dialup} from the Control Window drop down menu, or Click Settings on the Toolbar.

Setting up a Modem

At the Control

1. Choose {Tools}{Configurations}{Settings} from the Control Window drop down menu if updating a specific Control profile.
or
Click Settings on the Control Window Toolbar if updating the Standard Control profile.
2. Select Connectivity – Remote Dialup .
3. Select a Modem.

At the Client

1. Start the NetSupport Client Configurator, Basic or Advanced.
2. Select Connectivity - Dial-in Bridge.
3. Check the Bridge box and complete the form.

To adjust modem settings

Choose {Start}{Settings}{Control Panel}{Modems}.

Notes

- The adapter number used for dialling into a NetSupport Bridge is configured slightly differently to those used for connecting to a Client. The adapter number you set is the adapter number configured at the Bridge workstation. This is why the Remote Network wizard and Properties dialog displays all adapters and not just those set at the Control.
 - Use the Configurator at the Bridge workstation to determine the adapter number to use, then set this same adapter number at the Control for the Remote Network object.
 - If you attempt to dial a NetBIOS NetSupport Bridge and the adapter number is incorrect the connection will fail and an error message will be displayed.
-

Using NetSupport Over A Null Modem (Serial) Cable

If you do not have network adapters or modems, you can use a null-modem (serial) cable over dial-up networking to connect a NetSupport Control and Client.

Installing / configuring a serial cable device

In order to establish the connection between the two machines you must install and configure a serial cable device, the following section provides the steps required to do this on each operating system.

Windows Me/9x and Windows NT 4.0

The serial cable device is installed in the Modem utility in Control Panel and is listed under [Standard Modem Types] as "Dial-Up Networking Serial Cable between 2 PCs.". You will have to add this device manually as it will not be detected automatically.

The serial cable device is configured in the System utility in Control Panel. Click the Device Manager tab, double-click Modems, and then double-click Serial Cable On ComX (where 'x' is the COM port where your cable is attached.) Make sure the speed set here matches the speed of the machine that will be attached to the other end of the serial connection.

Windows 2000

The serial cable device is installed in the Modems tab within the Phone and Modem options utility in Control Panel and is listed under [Standard Modem Types] as "Communications cable between two computers". You will have to add this device manually as it will not be detected automatically.

The serial cable device is configured in the System utility in Control Panel. Click the Device Manager tab, double-click Modems, and then double-click Serial Cable On ComX (where 'x' is the COM port where your cable is attached.) Make sure the speed set here matches the speed of the machine that will be attached to the other end of the serial connection.

For additional information on null-modem (serial) cables, such as the proper pin-out configuration to work with the setups above, please see the following article in the Microsoft Knowledge Base:

Q142324 Cables That Are Compatible With Direct Cable Connection

Windows XP


Please see the following article in the Microsoft Knowledge Base
HOW TO: Set Up a Direct Cable Connection Between Two Windows XP-Based Computers (Q305621)

Configuring the NetSupport Client to listen for connections over the Serial cable

The NetSupport Client Bridge provides the interface between NetSupport Client and serial cable connection thus allowing the NetSupport Control to connect.

To configure the NetSupport Client Bridge perform the following at the Client.

1. Start the NetSupport Configurator, {Start} {Programs} {NetSupport} {NetSupport Configurator}.
2. Select the Basic or Advanced Configurator followed by Connectivity-Dial-in Bridge.



3. Choose the Transport protocol to run NetSupport over.
4. Choose whether to Load the Bridge at Startup.
5. In the Modem Section select the Serial cable device as installed above.

Configuring the NetSupport Control to connect to a NetSupport Client over a Serial cable

The NetSupport Control must firstly be configured to use the serial cable connection as follows:

1. Start the NetSupport Control, {Start} {Programs} {NetSupport} {NetSupport Control}
2. Select {Tools}{Configurations} from the Control Window drop down menu.
3. Choose Connectivity-Remote Dialup.
4. In the Modem Section select the Serial cable device as installed above.
5. Click Ok and followed by Close to exit the configuration dialog.

You must then configure a Remote Network to Dial the Client at the other end of the serial cable.

1. Select {Network}{Remote}{New} from the Control Window drop down menu.
2. The "Add a remote Network" Dialog will be displayed.
3. Enter a name for the connection and a description if you wish and click Next.
4. Enter 0 as the Telephone Number of the NetSupport Bridge to Dial.
5. In the Connectivity section select the Network transport to be used (this must be the same as that configured at the Client Bridge)
6. Once a dial up or serial link has been established, operation is the same as on a LAN.

Using NetSupport over the Internet


NetSupport Manager works across the Internet in much the same way as it does across Dialup Networking. It can be done to workstations with a static connection across a LAN or to a dialup account with ISP.

If your workstation can “see” a workstation running NetSupport you can connect to it, whether this is on the internet, via remote communications, a RAS Dialup Link or on your local LAN/WAN.

Note: While the following procedure can be used, NetSupport also provides a convenient Internet Gateway feature delivering web based remote control without the need for modifications to existing Firewall configurations.

To remote control a Client over the Internet

1. Connect both the Control and the Client to the Internet.
2. Choose {Client}{Quick Connect} from the Control Window drop down menus.
3. In the Quick Connect dialog, choose to connect via TCP/IP address and type in the IP address of the Client you wish to connect to. You should then be able to control as normal.



Finding an IP Address

The easiest way to find the IP address of the Client is to use the command line ipconfig.

DHCP

Workstations connecting via a modem link to an ISP will normally have a different IP address assigned to them each time they connect. You will therefore need to find out their address each time you wish to connect. This is done using the command line ipconfig.

ActiveX Control

In this chapter ...

Learn how to reach remote Clients via an Internet Browser using NetSupports ActiveX options.

ActiveX Control

It is possible to remote control a NetSupport Client using an Internet Browser. This is obtained through an ActiveX Control. All that is required is an Internet Server and an HTML page with the imbedded ActiveX Control.


The ActiveX Control program is installed by default as the CABinet file: PCIA.X.CAB. NetSupport also provides appropriate HTML pages, Control.htm and View.htm, accessible in \\program files\netsupport manager\web, which use the available ActiveX functions.

Note: View.htm requires Web Extensions enabling in the target Clients Configurator. Control.htm provides more flexibility in that it does not rely on individual Clients having Web Extensions enabled.

1. Launch Internet Explorer and type in the Clients IP address followed by Control.htm or View.htm. For example, 'HTTP://10.0.0.1/CONTROL.HTM'.

or

Load Control.htm directly from the program folder and enter the IP Address here.



Note: NetSupport Manager's ActiveX Control will not work with Netscape.

How to Access the Client as an Internet Server

The Client Internet Server is accessed from an Internet Browser by typing its IP address and port number in the browsers address field, and specifying the HTML page to download. The Internet Browser attempts to connect to the Internet Server at this address.

When the Control connects, it is connecting to the Internet Server section of the Client. It then requests the HTML document to be downloaded. The Client looks for this file in its Internet Server Directory.

If the HTML is found, the Client starts sending it to the browser. As it does, it looks for the variables in the HTML and replaces them as it goes. When the browser has received the entire page, it processes it locally to determine what to do.

When the Control comes across the <OBJECT>...</OBJECT> tag it checks in its registry to see if it has an ActiveX Control registered with this GUID. If it does then it is loaded and created on the Internet page. If it isn't available it checks in the object tag to see if there is a code base, this gives the browser an HTTP address where it can download the necessary Control. An additional piece of information supplied is the version number. Even if the Control is installed locally it will check its version number against the one in the Internet page to determine if it has the correct version, if not it will attempt to download and install a new version.

Web Extensions

It is possible to configure a Client as an Internet Server, which will supply simple Internet pages as HTML.

Additionally, the Client interprets certain variables when processing the HTML.

These are:

\$CLIENTNAME\$	Is replaced with the name of the Client
\$CLIENTADDR\$	Is replaced with the address of the Client
\$IPADDRESS\$	Is replaced with the TCP/IP address of the Client workstation
\$HSCREENRES\$	Is replaced with the Horizontal screen resolution
\$VSCREENRES\$	Is replaced with the Vertical screen resolution

These variables can appear anywhere within the HTML served by the Client Internet Server.

PCIAX.CAB – Cabinet File

The Cabinet file contains three files:

pciax.inf	This installs/uninstalls the necessary files.
pciax.dll	The ActiveX Control.
tcctl32.dll	NetSupport Manager TCP/IP Transport DLL.

When this file is downloaded the browser checks to see if its safe. It does this by checking to see if the file has a digital certificate, this doesn't guarantee that the Control is safe but it does guarantee that the Control hasn't been modified (with a virus or other malicious code). This file is created by NetSupport LTD and signed using a certificate and private key.

The certificate simply guarantee's that the binary file hasn't changed or been modified since NetSupport LTD signed it.

If the User trusts NetSupport LTD and continues with the download the files are extracted and the install file: pciax.inf is executed. This copies the files to a PCIAX folder under the SYSTEM directory. It then registers the Control in the registry making it available.

The browser then attempts to load the newly downloaded Control and create an instance of it to place on the Internet page.

The window_onLoad sub routine is then executed at the beginning of the HTML, and the Client's screen will appear.

ActiveX Control – HTML Examples

The following is some typical HTML which use all of the variables available with Client Web Extensions.

```
<html>
<head><script LANGUAGE="VBScript">
Sub window_onLoad()
call CTLAX.Init("")
CTLAX.Client = "$CLIENTADDR$"
call CTLAX.Connect()
CTLAX.ScaleToFit = 0
call CTLAX.View(2)
end sub

Sub CTLAX_Disconnect()
alert "Client " & CTLAX.Client & " has disconnected!"
end sub

</script>
<meta http-equiv="Content-Type" content="text/html; charset=iso-8859-1">
<title>NetSupport Active Control - Viewing $CLIENTNAME$</title>
</head>
<body>
<p>Viewing Client $CLIENTNAME$ - $CLIENTADDR$</p>
<p>
<object ID="CTLAX" WIDTH="$HSCREENRES$" HEIGHT="$VSCREENRES$"
CLASSID="clsid:04F26A51-3DA8-11D2-B8FC-00104B4F4F6A"
standby="Please Wait.. Loading PCIAx Control"
codebase="http://$IPADDRESS$/pciax.cab#version=1,0,0,2">
</object>
</p>
</body>
</html>
```

The first piece of HTML that handles the Control is at the beginning.

```
<script LANGUAGE="VBScript">
Sub window_onLoad()
call CTLAX.Init("")
CTLAX.Client = "$CLIENTADDR$"
call CTLAX.Connect()
CTLAX.ScaleToFit = 0
call CTLAX.View(2)
end sub
```

```
Sub CTLAX_Disconnect()
alert "Client " & CTLAX.Client & " has disconnected!"
end sub
```

```
</script>
```

This is some VBScript that sets up and communicates with the Control. Sub window_onLoad is a standard event that is called when the Internet Page is loaded.

The following commands are executed during this function, CTLAX is the identifier of the Control as defined in the <OBJECT> tag below:

```
CTLAX.Init("") Initialises the Control where * means use workstation name.
CTLAX.Client = "$CLIENTADDR$" Sets the address of the Client to connect to,
this is in the usual NSM format - ">10.0.0.5:5405"
CTLAX.Connect() Attempts to connect to the client
CTLAX.ScaleToFit = 0 Turns scale to fit off (as the Control will be set to the
size of the Client's screen).
CTLAX.View(2) Views the screen in Share mode, 1 is watch, 3 is Control and 0
is stop viewing.
```

The second sub routine, CTLAX_Disconnect, is an event provided by the PCIAX Control, this will be called if the Client is disconnected, it simply displays a message warning the User.

The main body of the page is some text with an embedded object. The embedded object is crucial.

```
<object ID="CTLAX" WIDTH="$HSCREENRES$" HEIGHT="$VSCREENRES$"
CLASSID="clsid:04F26A51-3DA8-11D2-B8FC-00104B4F4F6A"
standby="Please Wait.. Loading PCIAX Control"
codebase="http://$IPADDRESS$/pciax.cab#version=1,0,0,2">
</object>
```

This tells the Internet Browser that the Internet page contains an embedded binary object and it should attempt to create one locally.

The OBJECT tag has the following parameters:

ID	Gives the Control an identifier that we can use elsewhere on the Internet page.
WIDTH/HEIGHT	Specifies the width and height of the Control, these will be replaced with the actual screen resolution of the Client.
CLASSID	The GUID (Globally Unique Identifier) this is unique to NetSupport.
STANDBY	Text that is displayed while the Control loads.
CODEBASE	Tells the browser where to find the Control and its version if it isn't already installed.

NetSupport Scripting

In this chapter ...

Learn about NetSupports powerful Scripting language and how it can be used to automate repetitive tasks.

NetSupport Scripting Overview

NetSupport includes a powerful Scripting Language and Scheduler that allows you to automate the tasks you would normally perform repetitively in the NetSupport Control.

For example, you might set up a Script that runs unattended overnight to connect to a number of remote NetSupport Clients and upload or download files to them.

This is a simple case, but the Scripting also contains a wealth of Desktop Management functions such as the ability to interrogate Clients and retrieve information such as their free disk space; what operating system they are running etc.

You could even use NetSupport Scripting to distribute applications by using a combination of File Transfer, Remotely Execute Applications and edit the Registry.

Anything that you do manually with NetSupport Manager you can do automatically with NetSupport Scripting.

The following are just a few of the highlights: -

- A powerful structured language
- A wide range of text manipulation functions
- The ability to work with multiple connected Clients
- Local and remote operations are supported
- Full logging of activities
- The ability to supplement the system log with your own log messages
- All of the security features associated with the 32-bit control are available
- Your Scripts will not contain visible human readable passwords to develop your Scripts.

A full description of the Script Editor can be found in the on-line help.

Starting the Script Editor

The Scripting Editor allows you to edit and create automated NetSupport Manager Scripts.

To start the Script Editor

1. Choose {Start}{Programs}{NetSupport}{NetSupport Script Editor}.
2. The Script Editor Main Window will appear.

The Script Editor is divided into four main sections:

- The Menu Bar and Toolbar.
- The Command Window.
- Edit dialog Window.
- Script Output Frame.

Creating a simple Script

NetSupport Scripting contains so many functions that it is not possible to cover them all in a brief guide like this. Instead, we will take you systematically through creating, testing and running a simple Script. You can then explore the full functionality yourself.

To create a Script

1. Choose {File}{New} from the Scripting drop down menu bar.
2. A new Text Window, in which you will create your Script, will appear.
3. Double click on the Functions Folder and then again on Clients sub-folder. A list of functions relating to the Client will be displayed.
4. Select a function and holding down your mouse, drag and drop it into the Script dialog Window.
5. A dialog box will appear, prompting you for the variables you need to enter.
6. Select a transport for the Script to run on by selecting the SetTransport function, drag and drop it into the Script dialog Window.
7. A dialog box will appear, prompting you to set a transport.
8. Select which transports you wish to use and click **OK**. The correct syntax will automatically be inserted in the Script.
9. Select the Connect function, drag and drop it into the Script dialog Window.
10. Enter the Client(s) workstation to connect to and run your Script over.
11. Continue in this manner until you have completed your Script.

Notes

- To access help on any function, select it, right click and choose 'Display Help On ...'.
 - It is advisable to regularly check the syntax of your Script, choose {Run}{Check Syntax} from the drop down menus. The Script will then be checked and the results displayed in the output frame at the bottom of the screen.
-

Scheduling and Running a Script

You schedule a Script to run, using the NetSupport Scripting Agent. Start this from the NetSupport program Group.

The Scripting Agent contains many functions for tailoring the schedule to your exact needs. You create a schedule by choosing {Script}{Add} and selecting or adding the details you want in the Schedule dialog.

You can set many Scripts to run in the same schedule. You can even set the running of one Script to depend on the results from another.

NetSupport Scripting is an exceptionally powerful tool and there are an almost unlimited number of ways on which it can be used. Here are just a few ideas for you to consider: -

- Connect to Clients at remote sites overnight via a dial-up link and retrieve there days Sales.
- Connect to every Client on the Local LAN and retrieve its free disk space. Raise an alert if it is less than a certain limit.
- Send a command to every Client to log in to the File Server and download a database.
- Send a message to all Clients to be read by the Users first thing in the morning.
- Download an application overnight and use the Execute Command to run its Set-up.
- Update your NetSupport Clients to the latest version.

The list is endless.

Technical Reference

In this chapter ...

Additional technical information is provided which will further enhance your understanding of NetSupport features.

Unloading a NetSupport Client

Should you wish to unload the NetSupport Client on Windows ME/98/95, you can obtain a utility called Clunload.exe from our company website.

For NT/2000/XP

1. Use Net Stop Client32 from the command line.

Restarting a Client

In order to save any changes made to a Profile the file Client32.INI must be saved. Once saved, Windows should be restarted for these changes to take effect. On Windows XP, 2000 and NT you can stop and start the Client32.INI from the Client Configurator dialog box.

To save changes made to a Profile

1. Choose {Save} from the File drop down menu in the Client Configurator dialog box.

To restart the Client from the Client Configurator dialog box

1. Click on the Restart button on the toolbar.
2. A general information and licence NetSupport dialog box will appear.

Or,

1. From the File drop down menu, choose Stop Service.
2. A dialog box will appear informing you that the Client32 Service is being stopped.
3. From the File drop down menu, choose Restart Service.
4. A dialog box will appear informing you that the Client32 Service is being started.
5. A general information and licence NetSupport dialog box will appear.

Using Compression Effectively

Compression can be configured to three different settings, on, off or always. When compression is turned on, screen data and file transfer operations are compressed. However, if a file is transferred that is already stored compressed (such as a zipped file or certain graphic files) NetSupport will stop trying to compress it further after 64KBytes. If Use Compression is turned on the file is compressed no matter what its internal structure is, this can be useful for encrypting the file.

The compressing and decompressing of the information takes time. On a dial up link the overhead of compressing and decompressing is minimal compared to the transfer speed of the modems. However, on a local LAN, if either the Control and/or Client are low specification workstations the time taken to compress, transfer the data and then decompress can be greater than just sending the information directly. In this case, it is probably better to turn compression off.

You can use the Compression Tab in the About box to determine if file and screen information is being compressed efficiently. Time copying files of known sizes to determine if compression is speeding up your connection to the Client.

Using Cache Effectively

NetSupport can store areas of the Client screen in local memory. This enables the Control to determine whether it needs to get the area from the Client (relatively slow) or from local memory (fast), this is commonly referred to as a cache.

The Client and Control use the same size cache, the size of the cache for the Client is set via the Configurator, the size of the Control cache is set in the View settings. The lower of the Control and Client values is used.

Use the Cache tab of the About box to determine how efficiently the cache is currently working. If the hit rate is low then not many items have been requested from the cache (or your remote control session has not been very intensive). You could save memory by reducing the size of the cache. If the hit rate is high then the cache is being used heavily. In this case you may like to increase the size of the cache to speed up the remote control session.

The cache on the Control is created for each Client when it is viewed, bear this in mind if you regularly view multiple Client's screens. If each Client has a 4Mbyte cache and you view 6 of them, the Control will allocate 24Mb of memory. If the total size of all the caches exceeds your physical memory size then the operating system will start paging memory to disk, this will affect the performance of the cache.

If you have Clients with different cache sizes set, configure the Controls to be as big as the largest Client setting. That way the Control will always allocate the largest cache the Client can support.

Remote Client Hardware and Software Inventories

For many support teams an important part of the problem resolution process is knowing not only what platform the workstation is running, but its hardware specifications and the applications installed on the workstation. For this reason, NetSupport Manager provides the tools to supply a full inventory of the remote workstation.

In addition to its sophisticated hardware/software reporting, where over 50 items of information are collected specifically about the hardware or environment of the client PC, you can obtain details of applications in memory, installed hot-fixes, processes running and installed services.

As well as the real-time reporting, NetSupport Manager also provides the tools, security permitting, to allow you to remotely stop and start services, end applications and more.

Note: In order to use the HTML based features within NetSupport's Inventory options, Internet Explorer 4 or above is required.

To Retrieve A Client Inventory


1. Select the required Client icon in the Control Window List View.
2. Choose {Client}{Inventory} from the Control Window drop down menu.
or,
Right click on the Client icon and choose Inventory.
or,
Click the Actions icon on the Control toolbar and choose Inventory.
or,
While Viewing the Client screen, choose the Inventory icon from the View Window toolbar.
3. The Inventory Window for the selected Client will appear.

Notes:

- If a Client is not selected, an inventory of the local machine will be retrieved.
 - Once collected, the various Client inventories are stored locally in the NetSupport Manager program folder meaning that you do not need to be connected to the target PC to be able to view the information at a later date. Simply select the required Client from the List View and choose the Inventory option. However, if you subsequently want to refresh the inventory you do need to connect to the target PC.
-

The Inventory Window

The Inventory Window is the primary interface for accessing the wealth of information that NetSupport's inventory feature provides.



The Window is organised as follows:

The Title Bar

This displays the name of the remote Client PC, or if a Client was not selected, the Local machine, whose system inventory is being viewed.

The Menu Bar

Contains a series of drop down menus that can be used to access the various tools and configuration utilities.

The Toolbar

The Tool Bar contains shortcuts to many of the most frequently used tasks and tools. Clicking on an individual item takes you straight to that task or function, eliminating the need to work through the drop down menus. Positioning the cursor over an icon will display a brief description of its function.

Hardware Tab

Over 50 items of information are collected specifically about the hardware or environment of the client PC, providing all the key information needed to assist in speedy problem resolution.

The screenshot shows the 'Hardware' tab in NetSupport Manager. It displays various system details in a structured layout. At the top, there are tabs for Hardware, Software, Hot Fixes, Applications, Processes, and Services. The main content area is divided into sections for Video Adapter and Storage. The Video Adapter section shows details for Video Adapter 1, Adapter RAM, DAC Type, Desktop Monitor 1, Video Resolution, and Refresh Rate. The Storage section shows details for Physical Disk 1, Capacity, PT_XXC, File System, Size, CD Rom / DVD 1, Drive Letter, Floppy 1, and Drive Letter. A progress bar indicates 11% Free space, with a breakdown of 25% Free Space, 25% Used, and 10% Reserved.

Video Adapter	
Video Adapter 1:	S3 Graphics Inc. ProSavage
Adapter RAM:	16 MB
DAC Type:	S3 SDAC
Desktop Monitor 1:	Default Monitor
Video Resolution:	1024 x 768 x 32 bit
Refresh Rate:	60 Hz
Storage	
Physical Disk 1:	SAMSUNG SV2011H
Capacity:	18.68 GB
PT_XXC:	C:
File System:	FAT
Size:	2.00 GB
CD Rom / DVD 1:	SAMSUNG CD-ROM SC-152L
Drive Letter:	E:
Floppy 1:	Floppy disk drive
Drive Letter:	A:

Note: The Inventory functions included with NetSupport Manager are designed to run over TCP/IP. The Network adapter details will not be displayed if TCP/IP is not installed.

Software Tab


Provides a full software inventory report for any selected client PC. Includes the name of each installed product, the manufacturer, product icon, version number and even the associated exe file.

The screenshot shows the 'Software' tab in NetSupport Manager. It displays a 'Software Inventory Summary' for a client PC named 'TEST25'. The summary is last updated on 11 Nov 2006 at 14:23:31. Below the summary is a table listing installed software products, their companies, folder names, versions, and file names.

Description	Company	Folder Name	Version	File Name
Address Book	Microsoft Corporation	Outlook Express	6.00.2600.0000	wab.exe
CrossTec EMS Console	CrossTec Corp	Console	2, 6, 0,261	DNAConsole.exe
CrossTec EMS Recorder Wizard	CrossTec Corp	Console	2, 6, 0,202	RecorderWizard.exe
Internet Connection Wizard	Microsoft Corporation	Connection Wizard	6.00.2600.0000	icwconn2.exe
Internet Connection Wizard	Microsoft Corporation	Connection Wizard	6.00.2600.0000	inetwiz.exe
Internet Connection Wizard	Microsoft Corporation	Connection Wizard	6.00.2600.0000	icwconn1.exe
Internet Explorer	Microsoft Corporation	Internet Explorer	6.00.2600.0000	IEXPLORE.EXE
Internet Signup	Microsoft Corporation	Connection Wizard	6.00.2600.0000	isignup.exe
Java(TM) Web Start Launcher	Sun Microsystems, Inc.	bin	5.0.40.5	javaws.exe
Messenger Client	Microsoft Corporation	Messenger	Version 4.0	msmsgs.exe

Hot-Fixes Tab

NetSupport scans for and checks the status of any 'hot fixes' that have been installed on the selected Client workstation. The hot fix ID is listed along with its status. The hot fix ID links to the appropriate Microsoft support page where details of the fix can be found.






Hot fixes for TEST22




Last Updated : 26 Oct 2006 13:53:41

Hot Fixes (Click for more information)

-  [KB823980 Windows XP SP1](#)
-  [KB835732 Windows XP SP2](#)
-  [KB828741 Windows XP SP2](#)


-  HotFix verifies correctly.
-  HotFix fails verification.
-  Unable to Verify.

When verifying the status of each fix, NetSupport returns one of three indicators:

-  Verifies that the fix is present on the target PC and is current.
-  An expected file may not be present or is not the correct version. It would be advisable to install the fix again.
-  NetSupport was unable to gather the required information for it to be able to verify the status.


Applications Tab

The detection process uses NetSupport's new "intelliscan" technology to locate currently running applications on the target system rather than relying on the OS Add/Remove Records option. You need to be connected to the target PC in order to retrieve the information. The Control can choose to close a selected application from the list if required.



Processes Tab

Provides a list of processes currently running on the target PC. You need to be connected to the target PC in order to retrieve the information. The Control can choose to close a selected process from the list if required.



The screenshot shows the 'Processes' tab selected in the NetSupport Manager interface. The tab bar at the top includes Hardware, Software, Hot Fixes, Applications, Processes, and Services. The main area displays a table with two columns: 'Name' and 'Memory Usage'. The table lists various system and application processes along with their current memory consumption in kilobytes (K).

Name	Memory Usage
CALC.EXE	1,932 K
client32.exe	6,676 K
cmd.exe	576 K
csrss.exe	1,972 K
Explorer.EXE	13,772 K
IEXPLORE.EXE	10,980 K
lsass.exe	2,996 K
msmgs.exe	1,524 K
remcmdstub.exe	696 K
services.exe	1,732 K
smss.exe	152 K
spoolsv.exe	2,796 K
svchost.exe	1,648 K
svchost.exe	2,156 K
svchost.exe	2,428 K
svchost.exe	10,656 K
System	76 K
winlogon.exe	2,380 K
wordpad.exe	3,792 K

Note: The close process/application features are disabled by default. To enable, choose Advanced Client Configurator - Access Privileges.

Services Tab (NT/2000/XP only)

Provides a list of services currently running on the target PC. If you are not connected to the Client, this tab will not be displayed. The Control can stop and start services as required, unless this facility has been disabled in the Advanced Client Configurator - Access Privileges dialog.

Hardware Software Hot Fixes Applications Processes Services			
Name	Description	Status	
Alerter	Notifies selected users and compute...	Stopped	
Application Layer Gatew...	Provides support for 3rd party proto...	Stopped	
Application Management	Provides software installation servic...	Stopped	
Automatic Updates	Enables the download and installatio...	Running	
Background Intelligent T...	Uses idle network bandwidth to tran...	Stopped	
Client32		Running	
ClipBook	Enables ClipBook Viewer to store inf...	Stopped	
COM+ Event System	Supports System Event Notification ...	Running	
COM+ System Application	Manages the configuration and track...	Stopped	
Computer Browser	Maintains an updated list of compute...	Running	
Cryptographic Services	Provides three management service...	Running	
DHCP Client	Manages network configuration by r...	Running	
Distributed Link Tracking...	Maintains links between NTFS files wi...	Running	
Distributed Transaction ...	Coordinates transactions that span ...	Stopped	
DNS Client	Resolves and caches Domain Name ...	Running	
Error Reporting Service	Allows error reporting for services a...	Running	
Event Log	Enables event log messages issued ...	Running	
Fast User Switching Co...	Provides management for applicatio...	Stopped	
Help and Support	Enables Help and Support Center to ...	Running	
HID Input Service	Enables generic input access to Hum...	Running	
IMAPI CD-Burning COM ...	Manages CD recording using Image ...	Stopped	
Indexing Service	Indexes contents and properties of ...	Stopped	
InstallDriver Table Mana...	Provides support for the Running Ob...	Stopped	
Internet Connection Fir...	Provides network address translatio...	Stopped	
IPSEC Services	Manages IP security policy and start...	Running	
Logical Disk Manager	Detects and monitors new hard disk ...	Runnin...	

Using NetSupport's Security features effectively

NetSupport has a large number of security features that can be used to restrict access to the Control and Client. Knowing how these work together and their limitations is useful when planning your security policy.

Firstly, we recommend that if you want to restrict access to or protect a Client you do it at the Client, not at the Control.

There are a number of reasons for this. If the workstation contains sensitive information that you want to protect it is likely that the workstation will have some physical security measures. Perhaps it is located in a locked room, a restricted area or maybe it has some local security measures. For example, it runs NT using NTFS.

It doesn't matter how good the NetSupport Client's security is if people can just walk up to the workstation and access the information.

We recommend the following measures are used to secure a NetSupport Client. They are ranked from most secure to least secure. See the help in the Client Configurator for more information.

- Physically protect access to the workstation.
- Use a secure operating system such as NT and use its security to protect the workstation locally. i.e. use NTFS and User profiles for NT.
- Store the Client Configuration files in a secure area such as NT Server.
- Set Client Profiles that restrict the access rights that individual Control Users or Groups of Users have to what they actually need.
- Set a security key at the Control and Client. This only allows Controls to connect to the Client only if they have the same security key. For example, you can use this function to provide someone in a department with access to their departments' workstations only.
- Use the audit log/event log so you can determine who has connected and when.
- Disable features at the Client that you know the Control User will not need. For example, disable File Transfer or set Watch Only if you don't want people to manipulate the screen.
- For NT Client Workstations use the NT Security features such as validate USERID.

- Set a password on the Configurator and restrict access to who can run it.
- Password protect the Control workstation and set Control profiles for individual Users.
- Set restrictions in the Control Profile for accessing certain features like File Transfer, Viewing, Show etc.

Understanding IP Addresses

An IP address is made up of 4 bytes, each byte being made up of eight bits, which can have a value of 1 or 0. This gives possible IP addresses of 0.0.0.0 to 255.255.255.255.

Each IP address is also split into two portions, a network portion, which identifies the network the device is on, and the local or host portion, which identifies a particular device.

The subnet mask defines the position of this split between the network and host portions of the address, which is associated with the address. The subnet mask is also a four byte number. Each bit in the subnet mask that is set to 1 denotes that the corresponding bit in the IP address is part of the network portion.

For example if we have an IP address of 10.10.2.21 and a subnet mask of 255.255.255.0

IP Address	10	.	10	.	2	.	21
Subnet Mask	255	.	255	.	255	.	0
IP Address In Binary	00001010.00001010.00000010.00010101						
Subnet Mask in Binary	11111111.11111111.11111111.00000000						
Network Portion Of IP Address	00001010.00001010.00000010.00000000						
Host Portion Of IP Address	00000000.00000000.00000000.00010101						
Network Portion Of IP Address	10	.	10	.	2	.	0
Host Portion Of IP Address	0	.	0	.	0	.	21

Therefore when we send an IP packet to 10.10.2.21 we are actually sending a packet to device 21 on network 10.10.2.0

In the example above, the network 10.10.2.0 can have 256 host addresses, 0 to 255. However, two of the host addresses, the first and last, on each IP network are reserved. The reserved host address with all bits set to 0 is the Network Address, and the one with bits set to 1 is the broadcast address.

In our example network of 10.10.2.0

10.10.2.0 is the network address

10.10.2.255 is the broadcast address.

When an IP packet is sent to a networks broadcast address each device on the IP network will receive this packet.

It is this IP network broadcast address, which is used when configuring NetSupport Manager Control to browse on an IP subnet other than its own.

Understanding IPX Addresses

An IPX address is made up of two portions, a network portion, which denotes which network a particular device is attached to, and a node portion, which denotes the physical device on the network.

The network portion of an IPX address is an eight digit hexadecimal number, valid network addresses ranging from 00000000 to FFFFFFFF. There are no reserved IPX network numbers, however each IPX network on an internetwork must have a unique network number.

The node portion of an IPX address is a 12 digit hexadecimal number, this is normally the MAC (Media Access Control) address. The MAC address is a unique number that is burnt into the EPROM of a network card by the cards manufacturer

Below is an example of an IPX address

Network	Node
00000001	: 0000E8D67295

When configuring a NetSupport Manager Control to browse a remote IPX network you must know the IPX network address of the remote network.

The NetSupport Client can display the IPX network number of the IPX network to which it is attached.

1. From the Client Main Window select {Help}{About the Client}.
2. Click Transports.

The IPX address is shown in full. Make a note of the network portion of this address, it will be required when configuring the Control.

Using Command Line Instructions

The NetSupport Control program, PCICTLUI.EXE, can be called from the command line. A range of parameters are available, enabling you to create shortcuts to many commonly used tasks.

Using these parameters you can, for example, create different Control profiles, set-up a connection to specific Clients, and then create a desktop icon to automatically execute the commands when required.

NetSupport Command Line Options

At the command line run 'PCICTLUI.exe', from the NetSupport Program folder, followed by the appropriate parameters:

/N Loads a specific Control Configuration. (Created using {Tools}{Configurations} from the Control Window drop down menu)

Note: When using control configuration profiles, it is advisable to password protect the configuration and keep the standard configuration unchanged to avoid locking yourself out of the control.

Syntax

PCICTLUI /NPROFILE NAME (where *profile name* = the stored configuration name)

/F Used with /N, restricts the control to only use the specified profile. By including this parameter, you prevent the Control User from being able to alter or add configurations.

Syntax

PCICTLUI /N/FPROFILE NAME

/C Connect to a specific Client by name or address.

Syntax

If connecting by IP address:

PCICTLUI /C">NN.NN.NN.NN" (where "NN.NN.NN.NN" = the IP Address)

If connecting by name:

PCICTLUI /C/NNNNNN (Where NNNNNN = client name)

/V Used in conjunction with /C, opens the View Window, in share mode, of the connected Client.

Syntax

PCICTLUI.EXE /C">NN.NN.NN.NN" /V

/VC Opens a View Window to the connected Client in Control Mode.

Syntax

PCICTLUI.EXE /C">NN.NN.NN.NN" /VC

/VW Opens a View Window to the connected Client in Watch Mode.

Syntax

PCICTLUI.EXE /C">NN.NN.NN.NN" /VW

/VS Opens a View Window to the connected Client in Share Mode.

Syntax

PCICTLUI.EXE /C">NN.NN.NN.NN" /VS

/E Used in conjunction with the /V options, opens the View Window without loading the Control. When the View Window is closed, the remote control session ends.

Syntax

PCICTLUI.EXE /C">NN.NN.NN.NN" /V /E

PCICTLUI.EXE /C">NN.NN.NN.NN" /VC /E

PCICTLUI.EXE /C">NN.NN.NN.NN" /VW /E

PCICTLUI.EXE /C">NN.NN.NN.NN" /VS /E

/G Connect to a defined group of Clients on startup.

Syntax

PCICTLUI.EXE /GNNNNN (where NNNNN = the Group name)

/D Dial into a Remote Network. Can be used in conjunction with /C

Syntax

PCICTLUI.EXE /DNNNNN /Cxxxxx (where NNNNN = the name of the Remote Network and xxxxx = the name of the Client to connect to)

/U Specify the protocol to use. Use IP for IPX/SPX, TC for TCP/IP, and NB*n* for NETBIOS where *n* = the stack 0-7.

Syntax

PCICTLUI.EXE /Unb1 (where *nb1* = netbios stack 1)

/R Display a NetSupport replay file.

Syntax

PCICTLUI.EXE /RNNNNN.rpf (where NNNNN.rpf = the file name)

/A Open a Chat session with a selected Client.

Syntax

PCICTLUI.EXE /CNN.NN.NN.NN /A

/I Retrieves a Hardware/Software Inventory from the selected Client machine.

Syntax

PCICTLUI.EXE /CNN.NN.NN.NN /I

Integration with Active Directory

NetSupport integrates with Microsoft's Active Directory structure enabling you to centrally manage Client configurations and launch remote control sessions. By creating an appropriate Group Policy you can apply standardised Client Configurations to Client machines without the need to visit individual desktops.

To make the task a little easier NetSupport supplies a ready-made Administrative Template, **NSMMASTER.ADM**, containing the configurable options. When you install NetSupport the template is copied to the NetSupport Manager program folder. In turn, you will need to copy this to the folder containing any existing ADM templates.

To Apply Client Configuration Changes via Active Directory

1. At the Domain Controller, select the Active Directory Users and Computers tool.
2. Decide at which level to apply the policies, domain or organisational. Right-click and select the Group Policy tab.
3. Select the desired policy to add the NetSupport template to and click Edit.
or
Select Add to create a new Policy.
4. In the Group Policy Editor under Computer Configuration, select Administrative Templates.
5. Right-click and select Add/Remove Templates.
6. Click Add and specify the location of NetSupport's ADM file and click Open. The new NetSupport policy will be added.
7. Click Close.

By default, each NetSupport policy option is disabled.

Each time you make a change to an option, the Group Policy refresh interval will determine when it is applied to Client machines. If a remote control session is not currently active, the Client will detect any changes to its own Administrative template and restart, applying the new settings. If a remote control session is open, the Client will restart at the next available opportunity.

For an explanation of the Configuration options that are available, refer to the Configuring The Client section.

Note: Please refer to the NetSupport Web site support area, www.netsupportsoftware.com/support for the latest information on Active directory policy files, instructions on upgrading from previous versions and applying NetSupport Client profiles within Active Directory.

Launching Remote Control Sessions

NetSupport's integration with Active Directory also enables you to perform a range of common remote control tasks.

In order to enable these features a NetSupport Manager installation must be performed by at least one user who has Domain Admin Rights.

1. At the Domain Controller, select the Active Directory Users and Computers tool.
2. Select the organisational unit where your computer accounts are held.
3. Right-click on the required computer account and select the required NetSupport operation.

Remote Control: Launches the Control and automatically opens a View Window to the selected Client machine.

Chat: Launches the Control and opens a Chat session with the selected Client.

Inventory: Retrieves a full Hardware/Software Inventory from the selected Client machine.

The NetSupport Client can be configured to validate user connections against members of Active Directory groups. See Configuring The Client - User Validation.

Glossary

ActiveX	The Microsoft portable application.
Attribute	Property of an object, such as a file or display advice.
Audio Support	Communicate with Clients or make announcements using preinstalled Audio hardware.
Auto-scroll	When Viewing a Client in a Window the area of the Clients screen may be too large to display in a Window. Auto-scroll provides an alternative to scroll bars whereby the scrollbars are turned off and the mouse position is used to re-locate the screen. Another alternative is to turn on Scale to Fit, which will resize the Clients screen to fit the available View Window.
Available Client	A workstation that a NetSupport Client is running on.
Baud rate	Number of times per second a signal changes in a communications channel. This rate varies in the number of bits it represents.
Bridge	A module loaded on any Client, either on a standalone or networked workstation that provides dial-in access to that workstation or to any workstation on the same network with a NetSupport Client running on it.
Broadcast Packets	A packet broadcast to all workstations on a LAN rather than being addressed to specific network addresses.
Browse	A means of searching the Network to auto-discover all NetSupport Clients and their Network addresses. Those found are displayed in the Browse Folder of the Tree View. Once you have connected to them they become Known Clients and are stored in the Clients Folder. They can then be used in later sessions without the need to Browse for them.

Cache	A means of storing recently used data in memory rather than having to regenerate or retrieve from disk. NetSupport caches screen information to reduce the need to re-send it over the Network. The higher the cache the more likely that the Client screen information will already be available to the Control and therefore the screen update time will appear faster.
CAPI	Common Application Programming Interface. An application programming interface for communicating over ISDN lines.
Chat	An online communication method between a Control and Client during a remote control session. A dynamic dialog window appears on each screen, both the Client and Control can type simultaneously and the messages will appear on both screens.
Client	The workstation that is to be taken over.
Compression	Method by which data is compacted for more efficient transmission. Data is compressed before transmission and decompressed afterwards.
Computer Name	A name typically used on Microsoft networks to identify a particular workstation on the network. Also called the Machine Name.
Configure	To set the security levels of a Client and Control workstation.
Connected Client	A network connection has been made between the Client and Control workstation, that will enable you to remotely control the Client workstation.
Control	The workstation that is used to take over another.
Control Mode	When a Client is being controlled in Control mode only the user at the Control can enter keystrokes and mouse movements. The user at the Client is locked out.

Delta File Transfer	A method for improving performance when using the File Transfer feature. If the file being transferred already exists in the destination directory, only changed parts of the file are updated.
Dialup networking	Connection in which a workstation calls a server and operates as a local workstation on the network.
Direct Serial Link	A connection between two workstations via a Null Modem Cable, operating as they would over a telephone link.
Dual Channel Bonding	A method for increasing bandwidth across an ISDN line. An ISDN line typically provides two channels, each of which can send/receive data at 64Kbps. By using both channels at once, calling the same location, you can double the speed to 128Kbps. However, by using both channels in this way, you are in effect making two calls.
Encryption	A method or algorithm used to scramble data being transferred to protect the data from being intercepted by unauthorised persons.
Execute	To launch an application on a Client workstation. The application must be installed or available to the Client workstation.
File Distribution	To move or copy a file(s) from a Control workstation to multiple Clients, simultaneously.
File Manager	To manage the files on the Control workstation.
File Transfer	To move or copy a file(s) from a Control workstation to a Client.
Firewall	Software to protect a network from another network (normally the Internet) where TCP/IP packets are only sent on certain ports.
Full screen mode	You can View a Clients screen in Windowed Mode, which allows you to see the NetSupport menus or Full Screen Mode. In full screen mode the whole of the Control's screen is used to display the Clients screen.

Gateway	A NetSupport component which provides a stable and secure method for connecting Clients and Controls via the Internet using HTTP. Delivers web based remote control without the need for modifications to existing Firewall configurations.
Group	A sub-set of NetSupport Clients that have been "Grouped" together for faster and easier access. Placing Clients in a Group allows you to connect to them in total and undertake actions such as file transfer to multiple Clients simultaneously. Groups are stored in the Group Folder.
Help Requests	An SOS message from a Client workstation to advice that they require assistance. Clients can specify which Control they send the help request to and the Control can specify when they are available to receive the message. Help Requests appear in the Help Request folder in the Tree View.
Hotkeys	Short cut key combinations, set in the Control and Client Configurators.
HTTP	Hypertext Transfer Protocol. The protocol used to transmit and receive all data over the World Wide Web. A NetSupport Gateway uses this protocol to enable connections to Clients/Controls across the Internet.
Icon	A picture or symbol that represents an object, task, command or choice users can select by pointing and clicking with a mouse.
Inactivity timeout	If a connected Control has not carried out any mouse, keyboard or file transfer activity for the specified period of time, the Client will assume that the connection is no longer required and disconnect automatically.
Initialise	1. To prepare for use. 2. In communications, to set a modem and software parameters at the start of a session.

Inventory	Can be run on a Client workstation, informing you of the hardware specifications and the applications installed on the workstation. See 'Remote Client Hardware and Software Inventories' in the Technical Reference section of this manual.
IP Address	Internet Protocol Address. An IP address is a number that identifies each sender or receiver of information that is sent in a packet across a network or the internet. Before a workstation can be remote controlled using the TCP/IP transport, it's IP Address must be known to NetSupport. See also TCP/IP.
IPX/SPX	A network protocol developed by Novell to enable workstations and servers to communicate. IPX/SPX is a routable, connection-orientated protocol that uses the MAC Address of the Network Adapter to uniquely identify the workstation and a network number to identify the network. SPX (Sequenced Packet Exchange) adds reliability to IPX (Internetwork Packet Exchange) by requesting acknowledgements to transmitted data. Windows NT implements IPX/SPX through NWLink.
Known Clients	Clients that have previously been connected to and whose Network address is therefore Known. Known Clients are stored in the Clients Folder in the List View.
LAN	Local Area Network. A group of workstations and other devices dispersed over a relatively limited area and connected by a communications link that enables any device to interact with any other device on the network.
Leased Line	Telephone line leased from a common carrier for private use. A leased line is faster and quieter, but generally more expensive than a switched telephone line.

List View	The List View displays the contents of the currently selected Folder in the Tree View. You can switch the display mode between icon and detailed view. The information within the List View can also be customised to show specific information, choose {View}{Toolbar - Customise}.
Log	To record the activities and events that take place on a workstation while it was remote controlled. The records are stored in a data file.
Login	To identify the user, using a name and password, to a workstation after connecting to it over a communications line.
Logoff	To end a session with a workstation accessed over a communications line. Also known as 'Logout'.
MAC Address	Media Access Control. On a network, the MAC address is a workstation's unique hardware number. The MAC address is used by the Media Access Control sublayer of the Data-Link Control (DLC) layer of telecommunication protocols. There is a different MAC sublayer for each physical device type. The Data-Link Layer is the protocol layer in a program that handles the moving of data in and out across a physical link in a network.
Machine Name	A name typically used on Microsoft networks to identify a particular workstation on the network. Also called the Computer Name.
Macro	See Script
Message	Way for a Control to communicate a message to multiple Clients, simultaneously. A dialog window appears on the Client screen, they must click OK for the message to disappear.
Modem	Hardware used to allow workstations to communicate over phone lines. It modulates a digital signal from a workstation to an analogue signal for transferral over phone lines.
Multimedia	Use preinstalled audio hardware to communicate and available avi/mpg video files to demonstrate to Clients.

Multiple Subscriber Number (MSN)	A facility whereby you can have more than one telephone number allocated to your ISDN line. In the case of NetSupport, you may want to restrict access to the Bridge to a specific MSN.
Named Configuration	Configurations for different Control users. By using a named configuration you can tailor the amount of functionality that a Control user will have according to their security level. For example, you might configure one user to have full functionality but another to have Watch only capability.
NetBEUI	See NetBIOS
NetBIOS	A protocol used to enable workstations to communicate in a Networked environment. NetBIOS, referred to as NetBEUI in the Microsoft environment, is a non-routable protocol suitable for small LANs. In the Windows environment you can load multiple NetBEUI stacks by attaching them to different virtual adapters.
NetBIOS Adapter	As you can have more than one NetBios stack loaded, each stack is allocated an Adapter Number by the operating system. So for example, NetBEUI may be allocated Adapter 1, NetBIOS over TCP Adapter 2 and so on.
Network Address	Unique address for each entity on the network, for example, server, workstation, router, printer.
Operating System	NetSupport runs over all Windows operating systems.
Physical Font	If a Client sends its screen information to a Control that does not have the same or similar fonts available, the Client will have to send the Control the full information required to display the data in the same font. Setting the 'Send Physical Fonts' option in the Advanced Client Configurator Remote Control options forces <i>TrueType</i> text to be sent as glyphs (character shapes), rather than as character codes. This guarantees that they will be displayed correctly at the Control. If Viewing a DOS or a Japanese font, adjust the setting 'Change DOS Font' or 'Change Japanese Font' in the Control Configuration View options.

Port Number	When communicating over TCP/IP, an application needs a Port Number to be able to identify which packets are specifically for that application. In the case of NetSupport, two default ports are used depending on the type of connection being made. The NetSupport Control uses port 5405 to send IP requests to Clients, the Client receiving incoming requests on the same port. To enable a Client to call the Control, port 5421 is used. If connecting to a NetSupport Client/Control over the Internet or anywhere that a router or firewall is involved it is important that the routing device be configured to allow packets on the appropriate NetSupport port.
Power Management	A technique that enables hardware and software to minimise system power consumption.
Print Capture	Redirects printer output from a local printer at the Client workstation to the printer or file at the Control.
Profile	A configured file that enables or disables functionality. By default NetSupport is installed with a single profile called Standard that is configured to allow full functionality.
Properties	Options that contain general contact, transport, address and system information on the Client or Group of Clients.
Protocol	See Transport
Proxy Servers	A method of using a server where workstations run/use software on another workstation by 'proxy'.
RAS	Remote Access Service is supplied with Windows NT and provides a means of connecting a remote workstation to a LAN using dial-up networking. It supports IPX, NetBEUI and TCP/IP. Once the connection has been made the remote workstation effectively becomes part of the LAN.
Remote Communications	Interaction with a Client by a remote workstation through a telephone connection or another communications line.

Remote Control	To control a Client workstation from a remote workstation.
Remote Deploy	A NetSupport utility enabling NetSupport Manager to be remotely installed and configured on multiple workstations simultaneously.
Remote Network Connection	A connection over a NetSupport Dial-up Link as opposed to over the LAN.
Remote Networking	Connecting to a LAN from an external site by means of a dial-up link.
Replay Files	A security video file that records all mouse movements and keyboard actions of a Control while they were connected to the Client. Replay files can be stored locally at the Client or at the Control.
Scale to Fit	See Auto-Scroll
Scan	Cycling through each connected Client displaying its screen at the Control. This is an alternative to Viewing multiple Clients simultaneously where definition can be lost if scale to fit is used.
Scheduling	Scripts can be run unattended overnight using the Scripting Agent.
Script	All NetSupport functions can be automated into a script, saving time and money when running repetitive tasks.
Security Key	An additional level of security that requires both the Control and the Client to have the same security key before the Client will allow a connection.
Selected Client	When you click on the Client icon in the List View the Client is selected for a 'one-to-one' session. Multiple Clients can be selected simultaneously.
Settings	During any control session where you may be working with more than one Client, you can tailor how each Client interacts with the Control. These settings only affect the Client during that session. For example, on one Client you may want to use compression because it is on a slow link, but on another you may want to turn compression off.

Share Mode	When a Client is being controlled in Share mode both the Client and Control can enter keystrokes and mouse movements.
Show	Displaying the Controls screen on a connected Client or Clients. This is the opposite of Viewing the Clients screen at the Control.
Silent Installation	An installation performed with no input from the user. You must pre-configure the Defaults.Inc file which is used to pre-set the options you would normally be prompted for during installation and Release.Ini file which enables you to pre-set the Advanced Client Configuration options.
Subnet	Subnetwork. See: Configuring the NetSupport Control for Subnet Browsing.
TAPI	T elephony A pplication P rogram I nterface. A standard program interface that lets you and your computer "talk" over telephones or video phones to people or phone-connected resources elsewhere in the world.
TCP/IP	Transport Control Protocol/Internet Protocol. A protocol used to enable workstations to communicate in a Networked environment. It is now the standard used across LAN's, WAN's, the Internet and it provides fast routable packets.
Tickle Packets	Normally when a Client is connected to a Control, they send each other a tickle packet every 30 seconds. This provides a check that the other end is still active and has not been turned off or subject to a network failure. There may be occasions when the use of tickle packets is undesirable, for example over an ISDN line where you wish the line to be dropped if there is no activity. You can turn off tickle packets at both the Client and the Control.
Transports	The networking protocol that the Control or Client has been configured to use. NetSupport supports IPX, NetBIOS, TCP/IP and HTTP. The Control can support all four simultaneously.

Tree View	The Tree View Pane in the main Window provides an explorer like structure for creating, displaying and organising NetSupport objects such as Clients and Groups.
Unattended	See Silent Installation
Video Driver	Software that captures video signals from the operating system then interprets them into colours and positions on a monitor.
Video skipping	Sets a maximum number of screen updates to be sent to reduce network usage and improves performance.
Video Support	Show an avi or mpg file to Clients. Files must be local or available to the Client.
View	Controlling a Client workstation from a Control workstation.
VNC	Virtual Network Computing. Remote display system which allows you to view a desktop environment not only on the machine where it is running, but from anywhere on the Internet and from a wide variety of machine architectures. You can use NetSupport to connect to a Linux or MAC based system which has a previously installed VNC Client.
WAN	Wide Area Network. Network, usually constructed with serial lines, extending over distances. NetSupport Manager incorporates features that allow a NetSupport Manager installation on one network to be used to remotely manage workstations on another interconnected network.
Watch Mode	When a Client is being controlled in Watch mode only the user at the Client can enter keystrokes and mouse movements. The user at the Control is locked out.

Readers Comments

If you have any comments regarding the design, installation, configuration, or operation of this package please contact us.

We can never test our software on every possible combination of equipment. We may have inadvertently introduced a restriction or incompatibility, which affects you. We apologise for any shortcomings that you may discover. Please let us know so that we can resolve them.

UK & International

www.netsupportsoftware.com

Technical Support: *support@netsupportsoftware.com*

Sales (UK & Eire): *sales@netsupportsoftware.co.uk*

Sales (International): *sales@netsupportsoftware.com*

North America

www.netsupport-inc.com

Technical Support: *support@netsupport-inc.com*

Sales: *sales@netsupport-inc.com*

Germany, Austria and Switzerland

www.pci-software.de

Technical Support: *support@pci-software.de*

Sales: *sales@pci-software.de*

Japan

www.pcip.co.jp

Technical Support: *support@pcip.co.jp*

Sales: *sales@pcip.co.jp*

A

- access privileges, 192, 194
- access rights
 - for file transfer, 206
- active directory, 312
 - authenticate, 197
- ActiveX Control, 286
 - cabinet file, 288
 - HTML examples, 289
- adding Clients, 269
 - Mac systems, 88
- advanced Client browsing, 74
 - terminal server, 89
- advanced Client configuration, 178
- application
 - show application, 123
- applications running at Client. *See* inventory
- applications, using NetSupport, 17
- audio support, 124
 - adjusting microphone sensitivity, 126
 - adjusting speaker volume, 126
 - Client configuration, 216
 - Control configuration, 254
 - making announcements, 125

B

- basic Client configuration, 177
- beep
 - when Control receives help request, 260
 - while chatting, 152
 - while viewing, 217
- blanking Clients screens, 103
- broadcast show, 118, 229
- browsing, 68
 - advanced, 74
 - for Gateway Clients, 68
 - for terminal server Clients, 89
 - Gateways, 84
 - IPX network, 76
 - over a subnet, 74
 - over an IP subnet, 74
 - specify subnets, 229
 - understanding IP addresses, 307
 - understanding IPX addresses, 308
- buttons

- toolbar, 60

C

- cache, 211, 245, 297
- capture print output, 158, 251
- capture screen, 107
- change file attributes, 140
- chat
 - Client initiated, 169
 - Control initiated, 150
 - disable, 154, 194, 217
 - group chat, 150
 - initiate in explorer, 162
 - send audible beep, 152
- client
 - update, 93
- Client
 - acknowledge connection, 199
 - automatic login, 92
 - chat to a Control, 169
 - Client Main Window, 166
 - configuration, 177
 - connecting to Controls, 167
 - disconnecting a Control, 168
 - features, 165
 - inventories, 299
 - load bridge at startup, 186
 - power off, 94
 - power on, 94
 - properties, 272
 - raising a help request, 169
 - receiving messages, 170
 - remote installation, 35
 - resetting video driver, 170
 - restarting, 296
 - security. *See* security, at the Client
 - unloading, 296
- client automatic login, 92
- client automatic update, 93
- Client Configurator
 - access privileges, 192, 194
 - audio settings, 216
 - Client interface options, 217
 - Client settings, 217
 - connect options, 201
 - connectivity options, 180
 - dialin options, 186
 - disconnect options, 203

- enable web extensions, 189
- help request settings, 219
- profile options, 222
- remote control settings, 211
- replay file settings, 207
- security, 190
- set Client password, 190
- set Configurator password, 190
- set HTTP, 184
- set IPX, 182
- set NetBIOS, 183
- set Security key, 190
- set TCP/IP, 181
- set tickle period, 188
- show settings, 214
- user acknowledgement, 199
- user validation, 197
- view settings, 211
- Client settings, 227
- clients
 - organising clients, 112
- clipboard, 160
- command line instructions, 164, 309
- components
 - installing, 24
- compression, 238
 - file transfer, 262
 - use while viewing, 245
 - using effectively, 297
- configuration files
 - creating, 174
 - editing, 174
- configuring a gateway, 79
- configuring Clients, 177
- connect
 - by hostname, 229
- connecting to Clients
 - Linux, 52
 - Mac systems, 88
 - on different protocols, 73
 - over a remote IPX network, 76
 - over a subnet, 74
 - over an IP subnet, 74
 - pocket PCs, 50
 - quick connect, 71
 - terminal server, 89
 - through a gateway, 77
 - through firewalls, 86
 - through proxy servers, 86
 - through the Internet, 284
 - understanding IP addresses, 307
 - understanding IPX addresses, 308
 - using IP address, 71
- connecting to Controls, 167
 - through a gateway, 77
 - through firewalls, 86
 - through proxy servers, 86
 - through the Internet, 284
- connectivity
 - dialin options, 186
 - remote dialup at Control, 235
 - set HTTP, 184, 234
 - set IPX, 182, 231
 - set NetBIOS, 183
 - set NetBIOS connection, 233
 - set TCP/IP, 181, 229
- contact us, 325
- Control
 - adjusting microphone and speaker volume, 126
 - applications, 17
 - audio announcements, 125
 - audio support, 124
 - capture Client print output, 158
 - chat to Client, 150
 - clipboard, 160
 - connecting to Clients, 70
 - connecting to Clients, different protocols, 73
 - Ctrl+Alt+Delete, 98
 - dealing with help requests, 156
 - disconnecting Clients, 91
 - executing applications, 113
 - features, 13
 - file distribution, 146
 - file manager, 149
 - finding Clients on a gateway, 68
 - finding Clients on the network, 68
 - Internet, use over, 284
 - logout, 97
 - managing Control files, 149
 - messages, sending, 155
 - power management, 94
 - quick connect, 71
 - reboot, 97
 - recording replay files, 131
 - scanning clients, 105
 - security. *See* security, at Control
 - set name, 228
 - showing a Client's screen, 122
 - showing the Control screen, 118
 - starting, 54

- user defined tools, 116
- video support, 127
- viewing a Client, 101
- Control configuration
 - create desktop icons, 226
 - multiple profiles, 226
- Control Configurator, 224
 - advanced settings, 237
 - audio settings, 254
 - configure interface settings, 255
 - connectivity options, 229
 - Control interface settings, 255
 - event logging, 208, 240
 - file locations, 265
 - file transfer settings, 206, 262
 - general settings, 228
 - help request settings, 260
 - keyboard/mouse settings, 249
 - print capture settings, 251
 - protect configuration, 205
 - remote control settings, 245
 - remote dialup settings, 235
 - replay files, 241
 - restrict functionality, 258
 - security settings, 238
 - set HTTP connection, 234
 - set IPX connection, 231
 - set NetBIOS connection, 233
 - set TCP/IP connection, 229
 - startup settings, 243
 - terminal server settings, 89
 - user permissions, 242
- control panel video player, 129
- Control Window, 55
 - hide options, 255
 - list view, 67
 - toolbar, customise, 58
 - tree view, 64
- Ctrl+Alt+Delete, 98
- customisable display text, 199, 203, 221
- customise
 - toolbar, 58
- cut and paste, remotely, 160

D

- database, Client
 - adding, 269
 - deleting, 270
 - properties, 272

- renaming, 270
- default settings, customise. *See* customise
- deleting Clients, 270
- deleting files and directories, 139
- delta file transfer, 137, 262
- deploy
 - a Client configuration, 43
 - a NetSupport license file, 44
 - a NetSupport package, 39
 - getting started, 37
 - log files, 48
 - main window, 37
 - pre-define settings, 47
 - remote Install, 35
 - remote uninstall, 45
- DHCP
 - connect by hostname, 229
- dial-up links, 278
- directory
 - copying, 137
 - creating, 139
 - deleting, 139
 - synchronise, 142
- disable functionality, 192, 194, 217, 258
 - configure Control interface, 255
- disable NetSupport Protect, 267
- disconnect
 - a Client, 91
 - a Control, 168
 - all Clients, 91
 - configuration options, 203
- distributing files, 146
- dual channel bonding
 - enable at Client, 186
 - enable at Control, 235
- DVD
 - enable playback support, 211

E

- encryption
 - at Control, 238
 - force encryption, 201
- evaluation kits, 28
- event logging
 - enable at Client, 208
 - enable at Control, 240
- executing applications, 113
- explorer integration, 162

disable shell, 255

F

Fedora, 52

file

- change attributes, 140

- copying, 137

- copying between Clients, 139

- deleting, 139

- renaming, 140

file distribution, 146

File Distribution Window, 145

file locations, 265

file manager, 149

File Manager Window, 148

file transfer

- applying a filter in List View, 143

- arranging multiple Windows, 142

- between Clients, 139

- change file attributes, 140

- changing the sort orders, 144

- changing the view format, 143

- configuring access rights, 206

- control settings, 262

- copying files and directories, 137

- creating directories, 139

- deleting file and directories, 139

- delta file transfer, 137

- print file list, 141

- synchronising directories, 142

File Transfer Window, 135

- applying a filter in List View, 143

- arranging multiple Windows, 142

- changing the sort orders, 144

- changing the view format, 143

finding Clients on the network, 68

firewalls, 77, 86

G

gateway

- configuration utility, 79

- configure Client for HTTP, 184

- configure Control for HTTP, 234

- connecting Clients/Controls, 77

glossary, 314

groups, 273

- adding, 274

- chat, 150

- creating, 273

- properties, 275

332

removing, 274

H

hand-held devices, 50

hardware inventory, 299

help requests

- configure Control settings, 260

- configuring settings, 219

- dealing with, 156

- sending, 169

- use web based application, 219

hide

- interface settings, 255

hot fixes. *See* inventory

hotkeys, 249

HTTP

- connecting Clients/Controls, 77

- set at Client, 184

- set at Control, 234

I

icons

- create desktop icons, 226

- toolbar, 60

- use small toolbar icons, 55, 99, 107

- using command line instructions, 309

inactivity timeout

- set at Client, 211

initialising NetSupport, 54

install configuration options, 32

installing, 19

- components, 24

- evaluation kits, 28

- existing installation detected, 22

- gateway, 23

- on Linux machines, 52

- on Pocket PCs, 50

- on Windows, 20

- planning, 19

- properties for silent install, 32

- remote deploy, 35

- select an installation type, 23

- Server, 30

- silent/unattended, 31

- uninstalling, 28

- values.txt file, 31

instcfg.exe, 31

integration with active directory,
312

integration with explorer, 162
disable shell, 255

interface settings
configure, 255

Internet
ActiveX. *See* ActiveX Control
gateway, 77
use over, 284

inventory, 299
check for hot fixes, 302
disable at control, 258
disable features, 194
list applications, 302
list processes, 303
list services, 303
retrieve via explorer, 162
software and hardware, 299

IP connections, 71

IP subnet browsing, 74

IPX
set at Client, 182
set at Control, 231

IPX subnet browsing, 76

L

launching applications, 113

Linux support, 52

list view, 67

load bridge on startup, 186
load control from command line,
309

log files
during a remote deploy, 48
enable at Client, 208
log events at Control, 240

logging in clients, 92

logout, 97

M

MAC based systems
connecting to, 88

managing Clients, 268. *See* groups
add a new Client, 269
delete a Client, 270
rename a Client, 270
setting Client properties, 272

managing files
Control, 149

Mandrake, 52

max colour depth, 211

messages
customisable display text, 199,
203

messages, sending, 155

modem
at Control, 235
setting up, 280
using a serial link, 281

monitor mode, 110
configure settings, 255
multiple subscriber number
set at Client, 186
set at Control, 235

N

NetBIOS

set at Client, 183
set at Control, 233

NetSupport

applications, 17
components, 24
features, 13
internet gateway, 77

NetSupport deploy, 35
a Client configuration, 43
a NetSupport license file, 44
a NetSupport package, 39
getting started, 37
log files, 48
main window, 37
pre-define settings, 47
remote uninstall, 45

NetSupport Protect

disable desktop security, 267

NT

installation, 20
power management, 96
security, 178

num lock synchronisation, 249

O

organising Clients. *See also*
managing Clients
organising clients in the list view,
112

P

- parameters
 - command line, 309
 - silent installation, 32
- passwords, 238
- play sound
 - during chat session, 152
 - when help request arrives, 156
- pocket PC support, 50
- port number, 86
 - for gateway connection, 78
 - for HTTP connection, 78, 184, 234
 - for TCP/IP connections, 181
 - web extensions, 189
- power management
 - Client power off, 94
 - Client power on, 94
 - NT issues, 96
- pre-define deploy settings, 47
- print
 - deploy log file, 48
 - file transfer list, 141
- print capture, 158, 251
- processes running at Client. *See* inventory
- profiles, 174, 226
 - using command line instructions, 309
- prompt for connection reason, 238
- properties, Client, 272
- protecting the Client configuration, 205

Q

- quick connect, 71
 - disable at control, 258
- quiet mode, 217

R

- reboot, 97
- receive show options, 214
 - disable, 214
- record client activity, 132
- record local activity, 131
- Red Hat, 52
- remote clipboard, 160
- remote command prompt, 164
- remote communications, 277
- 334

- dual channel bonding, 186, 235
- optimising connections, 277
- planning, 278
- set MSN number, 186, 235
- setting up a modem, 280
- remote control
 - configure settings at Client, 211
 - configure view settings, 245
 - disable functionality, 258
 - viewing Clients, 101
- remote controlling a Client, 101
 - via explorer, 162
- remote deploy utility, 35
- remote install
 - a Client configuration, 43
 - a NetSupport license file, 44
 - a NetSupport package, 39
 - log files, 48
- remote uninstall, 45
- renaming Clients, 270
- replay files
 - create for all clients, 132
 - create for selected client, 132
 - enable at Client, 207
 - enable at Control, 241
 - record local activity, 131
 - recording, 131
 - showing, 118, 134
 - watching, 133
- requesting help, 169
- restarting a Client, 296

S

- scale to fit, 246
 - show window, 214
- scale to fit mode, 103
- Scan Window, 107
- scanning Client screens, 105
 - individually, 105
 - multiple, 106
- screen capture, 107
- screen scrape
 - set at Client, 211
 - set at Control, 245
- scripting, 292
 - creating a, 293
 - running, 294
 - scheduling, 294
 - starting the editor, 293
- scrollbars

- in show window, 214
- security
 - using effectively, 305
- security at Client
 - connect options, 201
 - disconnect options, 203
 - event logging, 208
 - force encryption, 201
 - set access privileges, 192, 194
 - set password, 190
 - set security key, 190
 - user acknowledgement, 199
 - user validation, 197
 - using log files, 208
- security at Control, 238
 - compression, 239
 - encryption, 238
 - event logging, 240
 - password, 238
 - replay files, 241
 - user permissions, 242
 - using log files, 240
- security key, 238
- send physical fonts, 211
- serial link, 281
- services at Client. *See* inventory
- settings, Client, 227
- set-up. *See* installing: planning
- shell extension
 - disable explorer shell, 255
- showing
 - a Client's screen, 122
 - an application, 123
 - broadcast show, 118
 - configure options at Client, 214
 - enable broadcast show, 229
 - replay files, 118, 134
 - the Control screen, 118
 - video support, 127
- silent installation, 31
 - install configuration options, 32
 - values.txt file, 31
- silent mode, 217
- software inventory, 299
- SOS messages
 - sending, 169
- starting NetSupport, 54
 - configure startup settings, 243
- subnet
 - browse IPX networks, 76

- configuring the control to browse, 74
- IP subnet browsing, 74
- understanding IP addresses, 307
- understanding IPX addresses, 308
- support for Linux, 52
- support for Pocket PCs, 50
- SuSE, 52
- switch desktop protection off, 267
- synchronisation, num lock, 249
- synchronising directories, 142

T

- TCP/IP
 - set at Client, 181
 - set at Control, 229
- terminal server, 89
- thumbnail view, 110
 - configure settings, 255
- tickle packets, 188, 237
- toolbar
 - buttons, 60
 - customise, 58
 - use small icons, 55, 99, 107
- transport
 - set for dialin, 186
 - set HTTP, 184, 234
 - set IPX, 182, 231
 - set NetBIOS, 183, 233
 - set TCP/IP, 181, 229
- tree view, 64

U

- understanding IP addresses, 307
- understanding IPX addresses, 308
- uninstalling, 28
- unloading a Client, 296
- url
 - route help requests to web based system, 219
- user acknowledgement, 199
- user defined tools, 116
- user permissions, 242
- user validation, 197
- using a serial link, 281

V

- values.txt file, 31
- video driver, resetting, 170

- video player, 127
 - control panel, 129
- video skipping, 247
- view modes, 101
- view settings, 104
- View Window, 99
 - use small toolbar icons, 99
- viewing, 101
 - blank Client screen, 103
 - configure default mode, 245
 - maximising view area, 102
 - multiple screens, 103
 - scale to fit, 103
 - use explorer to initiate, 162
 - view modes, 101
 - view settings, 104
- VNC Clients
 - connecting to, 88

W

WAN

- IP subnet browsing, 74
- IPX subnet browsing, 76
- subnet browsing, 74
- understanding IP addresses, 307
- understanding IPX addresses, 308

- web extensions, 189, 288
 - cabinet file, 288
- whiteboard, 150

Window

- chat, 152
- Client Main, 166
- Control Main, 55
- deploy, 37
- file distribution, 145
- file manager, 148
- file transfer, 135
- inventory, 300
- scan, 107
- view, 99

Windows 2000

- installation, 20
- security, 178

Windows 95/98

- installation, 20

Windows CE, 50

Windows explorer

- integration with NetSupport, 162

Windows Millennium

- installation, 20

Windows XP

- installation, 20